



z/OS

HCD
Reference Summary

First Edition, March 2001

This edition applies to Version 1 Release 1 of z/OS (5694-A01) and to all subsequent releases and modifications until otherwise indicated in new editions.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

IBM welcomes your comments. A form for readers' comments is provided at the back of this publication. If the form has been removed, address your comments to:

IBM Deutschland Entwicklung GmbH
Department 3248
Schönaicher Str. 220
D-71032 Böblingen
Federal Republic of Germany

Or by FAX:

From Germany: 07031-16-3456
Other countries: +(49)+7031-16-3456

Or electronically:

Internet e-mail: s390id@de.ibm.com
Web Page:
<http://www.ibm.com/servers/eserver/zseries/zos/hcm>

If you would like a reply, be sure to include your name, address, telephone number, or FAX number.

Make sure to include the following in your comment or note:

- Title and order number of this book
- Page number or topic related to your comment

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1994, 2001. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Chapter 1. Introduction	1
Chapter 2. Reference	3
Main Panel	3
IODF Naming Conventions	3
Main Configuration Tasks.	4
Selecting Actions.	5
Navigating in a Panel Flow	6
Navigating to Objects	7
Changing Connections.	8
Action Bar	10
Context Menu	12
Actions on OS and Related Objects	12
Actions on Processors and Related Objects.	14
Actions on Switches and Related Objects	16
Actions on Control Units and Devices	18
Actions on Configuration Packages and Related Objects.	20
Actions on Processors in an S/390 Microprocessor Cluster and Related Objects	21
Actions on Systems in an Active Sysplex	22
Commands	23
Online Help	25
How to Use the Dialog Efficiently	25
Display Positional Information.	25
Direct Editing	25
Keyboard and Function Keys	26
Prompt	26

Chapter 1. Introduction

This publication provides a brief overview of the Hardware Configuration Definition(HCD) tasks, the relationships of the configuration objects within HCD, and the navigation options among these objects. It also contains tables of actions (and their matching action codes) available for each object and information about the online help. It is organized as follows:

Main Configuration Tasks (see page 4)

Provides an overview of the main tasks supported by HCD.

Selecting Actions (see page 5)

Explains how to perform actions in HCD.

Navigating to Objects (see page 7)

Shows the organization of the object lists and how to navigate between these lists.

Changing Connections (see page 8)

Lists where connections can be changed between the different configuration objects.

Action Bar (see page 10)

Provides an overview of the action bar and of global actions that can be selected from it.

Context Menu (see page 12)

Provides an overview of the context menu and of global actions that can be selected from it.

Actions on OS and Related Objects (see page 12)

Lists available actions on OS, EDT, esoteric, generic objects, and consoles.

Actions on Processors and Related Objects (see page 14)

Lists available actions on processors, partitions, and CHPIDs.

Actions on Switches and Related Objects (see page 16)

Lists available actions on ESCON directors (switches), ports, and switch configurations.

Actions on Control Units and Devices (see page 18)

Lists available actions on control units and devices.

Actions on Configuration Packages and Related Objects (see page 20)

Lists available actions on configuration packages and configuration package objects.

Actions on Processors in an S/390 Microprocessor Cluster and Related Objects (see page 21)

Lists available actions on processors, on IOCDs and IPL attributes in an S/390 microprocessor cluster.

Actions on Systems in an Active Sysplex (see page 22)

Lists available actions on systems in an active sysplex.

Commands (see page 23)

Lists available commands.

Online Help (see page 25)

Provides an overview of the context-sensitive online help structure with hyperlinks.

If you are new to HCD, you will find much useful information in Getting started with this dialog (option 8 on the “Main Panel” on page 3).

Chapter 2. Reference

Main Panel

The HCD primary task selection panel (or main panel) is displayed when you start an HCD session.

```
OS/390 Release 9 HCD
Hardware Configuration
Select one of the following.
1_ 1. Define, modify, or view configuration data
    2. Activate or process configuration data
    3. Print or compare configuration data
    4. Create or view graphical configuration report
    5. Migrate configuration data
    6. Maintain I/O definition files
    7. Query supported hardware and installed UIMs
    8. Getting started with this dialog
    9. What's new in this release
For options 1 to 5, specify the name of the IODF to be used.
I/O definition file . . . 'SYS1.IODF00.WORK'      +
```

If you enter the name of a non-existing I/O definition file (IODF) in the main panel, HCD asks you to define a new work IODF.

IODF Naming Conventions

The format of the IODF data set name follows the standard TSO/E rules:

hhhhhhhh.IODFcc.yyyyyyyy.yyyyyyyy

<i>hhhhhhhh</i>	TSO/E high-level qualifier
IODFcc	IODF plus 2 hexadecimal characters
<i>yyyyyyyy.yyyyyy</i>	Optional qualifiers

A production IODF name has the same format as a work IODF; however, you must omit the optional qualifiers if you intend to use the IODF for IPL or dynamic activation.

Main Configuration Tasks

If you are using HCD for the first time, the standard sequence to define a configuration is:

1. Migrate an existing configuration into a work IODF:

On the main panel select **Migrate configuration data**. You can then do the following:

- Migrate IOCP data sets
- Migrate MVSCP data sets
- Migrate HCPRIO data sets
- Migrate switch configuration data

These options build a work IODF, or parts of it.

2. Change configuration definitions:

On the main panel select **Define, modify, or view configuration data**. On the resulting panel, select one option:

```
Define, Modify, or View Configuration Data
Select type of objects to define, modify, or view data.
1_ 1. Operating system configurations
    consoles
    system-defined generics
    EDTs
    esoterics
    user-modified generics
2. Switches
    ports
    switch configurations
    port matrix
3. Processors
    partitions
    channel paths
4. Control units
5. I/O devices
```

These options allow you to modify a work IODF. If you try to perform any of these options on a production IODF, HCD copies the production IODF into a newly built work IODF, on which you can perform the options.

3. Activate configuration data:

On the main panel select **Activate or process configuration data**. You can then select one of the following:

- ```
1. Build production I/O definition file
2. Build IOCDS
3. Build IOCP input data set
4. Create JES3 initialization stream data
5. View active configuration
6. Activate or verify configuration dynamically
7. Activate configuration sysplex-wide
8. Activate switch configuration
9. Save switch configuration
10. Build OS configuration data set
11. Build and manage S/390 microprocessor
 IOCDSs and IPL attributes
```

---

## Selecting Actions

To perform an action against an object:

1. Select the object (or a group of objects).
2. Select an action to be performed against the selected object.

You can select an object and the actions using the context menu or action codes.

### Using the context menu:

- To select an object [single select], enter a slash '/' to the left of the object.
- To perform the same action on a group of objects [extended select], use a left parenthesis '(' [top of range] and a right parenthesis ')' [bottom of range].
- Press the Enter key to display a context menu with a list of possible actions.
- Type the number or action code of the action into the entry field and press the Enter key.

**Note:** If there is only one action possible, the action is performed without showing the context menu.

### Using the action code:

- Type an action code to the left of the object, or an equal sign = to repeat the previous action code.
- To see a list of all available action codes, place the cursor in the action entry field to the left of an object and press the F4=Prompt key. The same context menu is shown as when selecting an object and pressing the Enter key.
- To get more information on action codes, place the cursor in the action entry field to the left of an object and press the F1=Help key.

### Removing selections:

- To remove all selections, action codes, and changes to a panel, press the F5=Reset key twice.

# Navigating in a Panel Flow

Most HCD tasks are performed in one step; when the step is complete, you can select the next task.

Some tasks, for example, defining a device, require the display of several panels. The navigation through the different panels is done with the Enter key and the function keys as follows:

**Enter** Displays the next panel. On the last panel of a task, it returns to the action list.

**F3=Exit** Returns to the action list. The values you entered are processed.

**F6=Previous** Returns to the previous panel. The values you entered are discarded.

**F12=Cancel** Cancels the action and returns to the list panel without processing any values. If you cancel more than one panel, you are asked to confirm the cancel operation.

Figure 1 illustrates the use of the Enter, F3, F6, and F12 keys.




Figure 1. Navigating within a Task

# Navigating to Objects

Figure 2 provides an overview of the different object lists within HCD. The leftmost numbers are the option numbers that must be selected on the main panel. Select the second number from the panel that follows.

Request the other lists by applying an action to a selected object within the displayed list (action code letter on the line between lists). In the action tables (see pages 12 to 21) you see the actions to request these lists. Usually, **Work with...** actions navigate to these lists.




Figure 2. Object Lists within HCD

---

# Changing Connections

To define a configuration with HCD, you need to establish connections between different objects. The following overview shows one way of changing the different connections in HCD and how to navigate to them. If there are attributes associated with the connections, these are listed as well.

---

## Connection Where to Change it

---

### Channel Subsystem Connections

---

**Processor – CU** To modify processor-CU settings like unit address ranges:

- Select CU.
- Select action **Change** (or action code **c**).
- Press the Enter key.
- Work on the *processor-CU* list.

---

**Processor – Device** You are prompted when you connect a device to a CU that is connected to a processor. To modify Processor-Device settings like unit address ranges:

- Select device.
- To change a device, select action **Change** (or action code **c**).
- To change a group, select action **CSS group change** (or action code **g**).
- Press the Enter key.
- Work on the *device-processor* list.

---

**Partition – Device** This is part of the connection between processor and device.

---

**CHPID – Partition** To modify the *access* or *candidate* list:

- On the *CHPID* list, scroll to the right.
- Type over the values (a or c) in the channel path/partition matrix.

---

**CHPID (CF receiver) – CHPID (CF sender)**

- On the *CHPID* list select any channel path and the action **Connect CF channel path** (or action code **f**).
- Select the source CHPID on the *CF channel path connectivity* list.
- To establish coupling facility (CF) channel path connections, use action **Connect to CF channel path** (or action code **p**).
- To disconnect, use action **Disconnect** (or action code **n**).

---

**CHPID – Port**

- Select the port of a switch on a *port* list.
- To connect, use action **Connect to channel path** (or action code **p**) on a *port* list.
- To disconnect, use action **Disconnect** (or action code **n**) on the *port* list.

You can change settings like **Dynamic switch ID** or **Entry switch** by selecting the action **Change** (or action code **c**) on the *CHPID* list or by writing over the appropriate values.

## Connection Where to Change it

---

### CHPID – CU

- Select CU.
  - Use action **Change** (or action code **c**).
  - Continue on the *processor-CU* list.
- 

### CU – Port

- Select a port of a switch.
  - Select action.
  - To connect, select **Connect to CU** (or action code **u** on a *port* list).
  - To disconnect, select action **Disconnect** (or action code **n**).
- 

### Port – Port

- Select a port of a switch.
  - Select **Connect to switch** (or action code **w** on a *port* list).
  - To disconnect, select action **Disconnect** (or action code **n**).
- 

### Port (in port matrix)

- Open a switch configuration of a switch using action **Work with port matrix** (or action code **s** on the *switch configuration* list).
  - Define dynamic or dedicated port connections by typing over values (or using action code **c**).
- 

### CU – Device

- Select device.
  - Select action **Change** (or action code **c**) or overwrite the CU field on the *device* list.
- 

## Operating System (OS) Connections

---

### OS – Device

To define settings like parameters and features:

- Select device.
- To change a device, select action **Change** (or action code **c**). To change a group of devices, select action **OS group change** (or action code **o**).
- Work on a *device-OS* list.

If you have invoked the *device* list from an OS, you can disconnect devices using the action **Disconnect** (or action code **n**)

---

### Esoteric – Device

This is part of the connection of a device to an OS.

- On the *OS* list, use action **Work with EDTs** for an OS (or action code **s**).
- Select action **Work with esoterics** (or action code **s**).
- To assign devices, select action **Assign devices** on the *esoteric* list (or action code **s**). This displays an *unassign/ assign devices to esoterics* list.
- Type over the values in the Assigned column to assign (Yes) or unassign (No) a device.

You can also establish an esoteric-device connection when adding or changing devices. The device is automatically known by the EDT when the device is assigned to one or more esoterics of the EDT.

---

## Action Bar

The different action bar choices and their meanings are listed below. Online help for the action bar can be requested by invoking extended help from any panel showing an action bar (under the action bar entry help, or using the F2 key from any field help panel, or by pressing the F1 key while the cursor is not on an input field). For a description of a specific action bar choice, move the cursor to that action and press the Enter key again.

| Action Bar       | Pull-down Menu                                                                                                                                                                                                                                                               | Meaning                                                                                                                                |
|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------|
| <b>Goto</b>      |                                                                                                                                                                                                                                                                              | <b>Displays a list of target objects to which you can go directly without having to navigate through the dialog.</b>                   |
|                  | Operating systems<br>EDTs ...<br>Esoterics ...<br>Generics ...<br>Consoles ...<br>Switches<br>Ports ...<br>Switch Configurations ...<br>Port Matrix ...<br>Processors<br>Partitions ...<br>CHPIDs ...<br>Control units<br>Devices<br>Migrate configuration data<br>Leave HCD |                                                                                                                                        |
| <b>Show/Hide</b> |                                                                                                                                                                                                                                                                              | Actions to show and hide parameters / features (only available on a <i>device</i> list invoked from the <i>OS configuration</i> list). |
| <b>Options</b>   |                                                                                                                                                                                                                                                                              | Action to select other switch configuration (only available on a <i>port</i> list).                                                    |
| <b>Filter</b>    |                                                                                                                                                                                                                                                                              | Actions to reduce or reset the list (Set filter, Clear filter).                                                                        |
| <b>Backup</b>    |                                                                                                                                                                                                                                                                              | Actions to backup the IODF (backup with prompt, backup without prompt).                                                                |
| <b>Query</b>     |                                                                                                                                                                                                                                                                              | Actions to query the types and models supported on your system, UIMs, and logs.                                                        |
|                  | List supported processors<br>List supported switches<br>List supported control units<br>List supported devices<br>List installed UIMs<br>View message log<br>View activity log<br>View IODF information                                                                      |                                                                                                                                        |
| <b>Help</b>      |                                                                                                                                                                                                                                                                              | <b>Provides different kinds of help.</b>                                                                                               |
|                  | Extended Help                                                                                                                                                                                                                                                                | Provides help about the function of the panel.                                                                                         |
|                  | Instruction Help                                                                                                                                                                                                                                                             | Provides help on how to interact with the panel (only on action list panels).                                                          |

| <b>Action Bar</b> | <b>Pull-down Menu</b> | <b>Meaning</b>                                     |
|-------------------|-----------------------|----------------------------------------------------|
|                   | Keys Help             | Provides help on the meaning of the function keys. |
|                   | Help for Help         | Describes how to use help.                         |

---

## Context Menu

To request an action from a context menu select an object on an action list panel (or type the action code letter next to the object) and press the Enter key. Only those actions appear in the context menu that are possible for the selected object.

---

## Actions on OS and Related Objects

The following list provides an overview of the different actions available on the context menu for OS, EDT, esoteric, generic and console objects. An arrow (→) in the description indicates that the action leads to one of the lists shown in Figure 2 on page 7.

| Action Code             | Action                            | Meaning                                                                                                |
|-------------------------|-----------------------------------|--------------------------------------------------------------------------------------------------------|
| <b>OS Configuration</b> |                                   |                                                                                                        |
| <b>a</b>                | Add like                          | To add an OS configuration definition like the one selected, without associated objects or references. |
| <b>r</b>                | Repeat (copy)                     | To copy the selected OS configuration, including its I/O devices, EDTs, esoterics, and consoles.       |
| <b>c</b>                | Change                            | To change an OS configuration definition.                                                              |
| <b>d</b>                | Delete                            | To delete an OS configuration and the associated objects and references.                               |
| <b>s</b>                | Work with EDTs                    | → <i>EDT</i> list                                                                                      |
| <b>n</b>                | Work with consoles                | To display a list of consoles and to add or delete consoles, or to change the order.                   |
| <b>u</b>                | Work with attached devices        | → <i>Device</i> list                                                                                   |
| <b>g</b>                | View generics by name             | → <i>Generic</i> list (sorted by name)                                                                 |
| <b>p</b>                | View generics by preference value | → <i>Generic</i> list (sorted by preference value)                                                     |

### EDT

|          |                                        |                                                                                                         |
|----------|----------------------------------------|---------------------------------------------------------------------------------------------------------|
| <b>r</b> | Repeat (copy)                          | To copy an EDT with its esoterics and device assignments and any EDT-dependent generic characteristics. |
| <b>c</b> | Change                                 | To change the EDT description.                                                                          |
| <b>d</b> | Delete                                 | To delete an EDT from the selected configuration, including all esoterics and device references.        |
| <b>s</b> | Work with esoterics                    | → <i>Esoteric</i> list                                                                                  |
| <b>g</b> | Work with generics by name             | → <i>Generic</i> list (sorted by name)                                                                  |
| <b>p</b> | Work with generics by preference value | → <i>Generic</i> list (sorted by preference value)                                                      |

### Esoteric

| <b>Action Code</b> | <b>Action</b>         | <b>Meaning</b>                                                                                                                                                                                                                                                                                                     |
|--------------------|-----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| r                  | Repeat (copy)         | To copy the esoteric device group with its assigned devices to a new esoteric name.                                                                                                                                                                                                                                |
| c                  | Change                | To change the esoteric group name and/or VIO eligibility.                                                                                                                                                                                                                                                          |
| d                  | Delete                | To delete the esoteric device group with all references to devices.                                                                                                                                                                                                                                                |
| s                  | Assign devices        | To assign or unassign devices. This displays an <i>assign/unassign device to esoteric</i> list on which you can type over the values in the Assigned column by either Yes or No.                                                                                                                                   |
| v                  | View assigned devices | To view the esoteric devices.                                                                                                                                                                                                                                                                                      |
| <b>Generic</b>     |                       |                                                                                                                                                                                                                                                                                                                    |
| c                  | Change                | To change the preference value and/or VIO eligibility (only valid when selecting action <b>Work with generics ...</b> on the <i>EDT</i> list).                                                                                                                                                                     |
| s                  | View devices          | To view all devices that are contained in the specified generic: <ul style="list-style-type: none"> <li>• <i>Generic</i> list by name</li> <li>• <i>Generic</i> list by preference value</li> </ul> <p><b>Note:</b> You can reach the <i>Generic</i> list from the <i>OS</i> list or from the <i>EDT</i> list.</p> |
| <b>Consoles</b>    |                       |                                                                                                                                                                                                                                                                                                                    |
| c                  | Change                | To change the selection order of a console.                                                                                                                                                                                                                                                                        |
| d                  | Delete                | To delete a console definition.                                                                                                                                                                                                                                                                                    |

## Actions on Processors and Related Objects

The following overview shows the different actions available on the context menu for processors, CHPIDs, partitions, and related objects. An arrow (→) in the description indicates that the action leads to one of the lists shown in Figure 2 on page 7.

| Action Code      | Action                       | Meaning                                                                                            |
|------------------|------------------------------|----------------------------------------------------------------------------------------------------|
| <b>Processor</b> |                              |                                                                                                    |
| a                | Add like                     | To add a processor definition like the one selected, without references and content.               |
| r                | Repeat (copy)                | To copy a processor definition, including partitions, CHPIDs and all object connections.           |
| c                | Change                       | To change processor definitions; for example type or model.                                        |
| i                | Prime serial number          | To update selected processors with the sensed data for the serial number of the local processor.   |
| d                | Delete                       | To delete a processor configuration and all its partitions, CHPIDs, and connections from the IODF. |
| p                | Work with partitions         | → <i>Partition</i> list                                                                            |
| s                | Work with attached CHPIDs    | → <i>CHPID</i> list                                                                                |
| u                | Work with attached devices   | → <i>Device</i> list                                                                               |
| k                | View related CTC connections | Displays defined CTC connections.                                                                  |
| v                | View processor definition    | Displays processor configuration definition.                                                       |
| <b>CHPID</b>     |                              |                                                                                                    |
| a                | Add like                     | To add a channel path with attributes like the one selected.                                       |
| c                | Change                       | To change a CHPID definition and its channel path access and candidate lists.                      |
| f                | Connect CF channel paths     | → <i>CF channel path connectivity</i> list.                                                        |
| g                | Aggregate channel paths      | To move all control units from a source CHPID to the selected target CHPID of the same processor.  |
| d                | Delete                       | To delete a CHPID definition and all references.                                                   |
| s                | Work with attached CUs       | → <i>CU</i> list                                                                                   |
| v                | View channel path definition | To display the CHPID definition and its channel path access and candidate lists.                   |
| w                | View connected switch(es)    | To display dedicated connections of related switch configurations.                                 |

| <b>Action Code</b> | <b>Action</b>                | <b>Meaning</b>                                                                            |
|--------------------|------------------------------|-------------------------------------------------------------------------------------------|
| <b>k</b>           | View related CTC connections | Displays defined CTC connections.                                                         |
| <b>h</b>           | View graphically             | To display graphically a channel path in relation to attached switches, CUs, and devices. |

**Coupling Facility CHPIDs in the CF receiver / CF sender Channel Path Connectivity List**

|          |                                   |                                                                                                                                         |
|----------|-----------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| <b>p</b> | Connect to CF channel path        | To select a source and a destination channel path for a CF connection, and to define a CF control unit and devices for that connection. |
| <b>n</b> | Disconnect                        | To break a CF connection; the CF control unit and CF devices are deleted implicitly.                                                    |
| <b>v</b> | View source CHPID definition      | To display the definition of a source CHPID and its access and candidate lists.                                                         |
| <b>t</b> | View destination CHPID definition | To display a definition of a destination CHPID and its access and candidate lists.                                                      |
| <b>s</b> | View CF control unit and devices  | To display the CF control unit and devices that are used for a specific connection.                                                     |

**Partition**

|          |                                         |                                                                                                                                                                                             |
|----------|-----------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>r</b> | Repeat (copy)                           | To add a partition definition with the same access and candidate list entries as the one selected.                                                                                          |
| <b>x</b> | Transfer (move) partition configuration | To transfer an entire partition configuration (CUs and devices), or a subset of it, to another partition (target partition can be in a different processor configuration of the same IODF). |
| <b>c</b> | Change                                  | To change a partition definition.                                                                                                                                                           |
| <b>d</b> | Delete                                  | To delete a partition definition and all references.                                                                                                                                        |
| <b>v</b> | View attached CHPID                     | To display a list of CHPIDs known to the partition (read-only)                                                                                                                              |
| <b>s</b> | View attached control units             | To display a list of CUs attached to the partition (read-only)                                                                                                                              |
| <b>u</b> | View attached devices                   | To display a list of devices attached to the partition (read-only)                                                                                                                          |
| <b>k</b> | View related CTC connections            | Displays defined CTC connections.                                                                                                                                                           |
| <b>h</b> | View graphically                        | To display graphically a partition in relation to attached switches, CUs, and devices.                                                                                                      |

## Actions on Switches and Related Objects

The following overview shows the different actions available on the context menu for switches and related objects (switch configurations and ports). An arrow (→) in the description indicates that the action leads to one of the lists shown in Figure 2 on page 7.

| Action Code                | Action                          | Meaning                                                                                                                                 |
|----------------------------|---------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| <b>Switch</b>              |                                 |                                                                                                                                         |
| a                          | Add like                        | To add a switch definition with the same attributes as the one selected.                                                                |
| c                          | Change                          | To change a switch definition.                                                                                                          |
| i                          | Prime serial number             | To update the selected switches with the sensed data for the serial number.                                                             |
| x                          | Move ports                      | To move ports within the selected switch or from other switches to the selected target switch.                                          |
| d                          | Delete                          | To delete a switch definition.                                                                                                          |
| p                          | Work with ports                 | → <i>Port</i> list                                                                                                                      |
| s                          | Work with switch configurations | → <i>Switch configuration</i> list                                                                                                      |
| h                          | View graphically                | To display graphically a switch in relation to attached processors, CUs, and devices.                                                   |
| <b>Port</b>                |                                 |                                                                                                                                         |
| c                          | Change                          | To change a port definition.                                                                                                            |
| p                          | Connect to channel path         | To connect ports to channel paths.                                                                                                      |
| u                          | Connect to CU                   | To connect ports to CUs.                                                                                                                |
| w                          | Connect to switch               | To connect a port to a port of another switch.                                                                                          |
| n                          | Disconnect                      | To disconnect connected units (ports of other switches, CUs, or CHPIDs).                                                                |
| i                          | Prime port name and connections | To update the selected ports with the sensed data for the port names, the connected processor/channel paths, control units or switches. |
| s                          | Work with dynamic connections   | To view and process dynamic connection attributes (defined in a specific switch configuration). → <i>Dynamic Connection</i> list.       |
| <b>Dynamic connections</b> |                                 |                                                                                                                                         |
| a                          | Allow                           | To set the attribute Allow for the dynamic connection between the designated port and the selected ports.                               |
| p                          | Prohibit                        | To set the attribute Prohibit for the dynamic connection between the designated port and the selected ports.                            |

| <b>Action Code</b>          | <b>Action</b>               | <b>Meaning</b>                                                                                              |
|-----------------------------|-----------------------------|-------------------------------------------------------------------------------------------------------------|
| f                           | Use default connection type | To set the default attribute for the dynamic connection between the designated port and the selected ports. |
| <b>Switch configuration</b> |                             |                                                                                                             |
| r                           | Repeat (copy)               | To copy a switch configuration.                                                                             |
| c                           | Change                      | To change a switch configuration definition.                                                                |
| g                           | Generate Matrix             | To create a port matrix for a switch configuration according to the logical paths already defined.          |
| d                           | Delete                      | To delete a switch configuration.                                                                           |
| s                           | Work with port matrix       | → <i>Port</i> matrix                                                                                        |
| <b>Port matrix</b>          |                             |                                                                                                             |
| c                           | Change                      | To change port definition (name, block/unblock, dedicated port).                                            |
| a                           | Allow all                   | To set the <b>Allow all dynamic connections</b> attribute.                                                  |
| p                           | Prohibit all                | To set the <b>Prohibit all dynamic connections</b> attribute.                                               |
| f                           | Use default                 | To reset to user-defined default <b>dynamic connection allowed/prohibited</b> attributes.                   |
| v                           | View connected units        | To view all units connected to the selected port(s) (CUs, processors, and ports of other switches).         |

## Actions on Control Units and Devices

The following overview shows the different actions available on the context menu for control units and devices. An arrow (→) in the description indicates that the action leads to one of the lists shown on Figure 2 on page 7.

| Action Code   | Action                         | Meaning                                                                                                                                             |
|---------------|--------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>CU</b>     |                                |                                                                                                                                                     |
| a             | Add like                       | To add a CU with the same attributes as the one selected.                                                                                           |
| c             | Change                         | To change a CU definition.                                                                                                                          |
| i             | Prime serial number            | To update the selected control units with the sensed data for the serial numbers.                                                                   |
| d             | Delete                         | To delete a CU definition.                                                                                                                          |
| s             | Work with attached I/O devices | → <i>Device</i> list                                                                                                                                |
| v             | View CU definition             | To display CU definitions and connections to CHPIDs and processors.                                                                                 |
| l             | View logical CU information    | To view information about the physical CUs that make up the logical CU.                                                                             |
| k             | View related CTC connections   | Displays defined CTC connections.                                                                                                                   |
| h             | View graphically               | To display graphically a CU in relation to attached processors, switches, and devices.                                                              |
| <b>Device</b> |                                |                                                                                                                                                     |
| a             | Add like                       | To add a device with the same attributes as the one selected.                                                                                       |
| c             | Change                         | To change a device definition.                                                                                                                      |
| g             | CSS group change               | To change the channel subsystem definition(s) for one or more devices.                                                                              |
| o             | OS group change                | To change the operating system I/O definition(s) for one or more devices.                                                                           |
| t             | Device type group change       | To change the device type for one or more devices.                                                                                                  |
| e             | Attribute group change         | To change the dynamic attribute for all selected devices (only valid on a <i>device</i> list reached from a <i>OS configuration</i> list.)          |
| n             | Disconnect from OS             | To delete all device references to the selected operating system (only valid on a <i>device</i> list invoked from an <i>OS configuration</i> list). |
| i             | Prime serial number and VOLSER | To update the selected I/O devices with the sensed data for the serial numbers. For DASD devices, the sensed VOLSER is also updated.                |
| d             | Delete                         | To delete a device.                                                                                                                                 |

| <b>Action Code</b> | <b>Action</b>                | <b>Meaning</b>                                                                                |
|--------------------|------------------------------|-----------------------------------------------------------------------------------------------|
| v                  | View device definition       | To display device attributes and connections to CUs, processors and OSs.                      |
| l                  | View logical CU information  | To view information about the CUs that the device is connected to (making up the logical CU). |
| k                  | View related CTC connections | Displays defined CTC connections.                                                             |
| h                  | View graphically             | To display graphically a device in relation to attached processors, CUs, and devices.         |

**Actions for device groups: Do one of the following:**

- Mark all devices of the group with the same action code in the action entry field.
- Mark the beginning and end of the group with parentheses in the action entry field; then select the action from the context menu.

---

## Actions on Configuration Packages and Related Objects

The following overview shows the different actions available on the context menu for configuration packages and configuration package objects. An arrow (→) in the description indicates that the action leads to one of the lists shown on Figure 2 on page 7.

Display the Configuration Package list by selecting **Maintain I/O definition files** from the main panel and **Work with Configuration Packages** from the panel that follows.

| Action Code                         | Action                                  | Meaning                                                                                         |
|-------------------------------------|-----------------------------------------|-------------------------------------------------------------------------------------------------|
| <b>Configuration package</b>        |                                         |                                                                                                 |
| a                                   | Add like                                | To add a configuration package with the same attributes as the one selected.                    |
| d                                   | Delete                                  | To delete a configuration package.                                                              |
| s                                   | Work with configuration package objects | → <i>Configuration Package Object</i> list                                                      |
| x                                   | Transmit configuration package          | To transmit I/O configuration data from a production IODF to a target system.                   |
| <b>Configuration package object</b> |                                         |                                                                                                 |
| a                                   | Add like                                | To add a configuration package object with the same attributes as the one selected.             |
| m                                   | Merge                                   | To merge I/O configuration data from another IODF into a work IODF.                             |
| r                                   | Replace                                 | To replace I/O configuration data in a work IODF with I/O configuration data from another IODF. |
| d                                   | Delete                                  | To delete a configuration package object.                                                       |

No special action is provided for editing configuration packages. Edit a configuration package by overwriting the information displayed on the Configuration Package list.

---

## Actions on Processors in an S/390 Microprocessor Cluster and Related Objects

The following list provides an overview of the different actions available on the context menu for CPCs/processors configured in an S/390 microprocessor cluster and related objects (IOCDSs and IPL attributes in an S/390 microprocessor cluster). An arrow (→) in the description indicates that the action leads to one of the lists shown in Figure 2 on page 7.

| Action Code                                      | Action                               | Meaning                                                                                                                                                 |
|--------------------------------------------------|--------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Active CPCs/Processors</b>                    |                                      |                                                                                                                                                         |
| <b>s</b>                                         | Work with IOCDS                      | → <i>IOCDS</i> list                                                                                                                                     |
| <b>i</b>                                         | Work with IPL attributes             | View the IPLADDR and IPLPARAM values used for the last IPL for CPCs in an S/390 microprocessor cluster and edit the values to be used for the next IPL. |
| <b>p</b>                                         | Select other processor configuration | To display definitions of additional IODF processors associated with a specific CPC.                                                                    |
| <b>IOCDSs in an S/390 microprocessor cluster</b> |                                      |                                                                                                                                                         |
| <b>u</b>                                         | Update IOCDS                         | To write the processor configuration information to the selected IOCDSs of the designated CPCs.                                                         |
| <b>s</b>                                         | Switch IOCDS                         | To switch the IOCDS pointer for next POR.                                                                                                               |
| <b>e</b>                                         | Enable write-protection              | To prevent the selected IOCDSs from being updated.                                                                                                      |
| <b>w</b>                                         | Disable write-protection             | To allow the selected IOCDSs to be updated.                                                                                                             |

---

## Actions on Systems in an Active Sysplex

The following list provides an overview of the different actions available on the context menu for systems in an active sysplex.

| Action Code                 | Action                                       | Meaning                                                                                                                                    |
|-----------------------------|----------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Systems in a sysplex</b> |                                              |                                                                                                                                            |
| <b>o</b>                    | Activate software configuration only         | To activate the software configuration dynamically.                                                                                        |
| <b>a</b>                    | Activate software and hardware configuration | To activate a configuration dynamically if both hardware and software changes are allowed.                                                 |
| <b>t</b>                    | Resume activation of target configuration    | To force the activation of the system.                                                                                                     |
| <b>r</b>                    | Reset source configuration                   | To reset the original configuration.                                                                                                       |
| <b>s</b>                    | Switch IOCDS for next POR                    | To specify the IOCDS to be used for the next POR.                                                                                          |
| <b>m</b>                    | View activate messages                       | To display the messages as the result of the activation request.                                                                           |
| <b>d</b>                    | Delete activate messages                     | To delete the messages of the activation request.                                                                                          |
| <b>v</b>                    | View configuration status                    | To get additional information if the activation is rejected.                                                                               |
| <b>k</b>                    | Verify active configuration against system   | To display a list comparing all sensed paths from the system to the definitions in the active IODF.                                        |
| <b>l</b>                    | Verify target configuration against system   | To display a list comparing all sensed paths from the system to the definitions in the target IODF.                                        |
| <b>b</b>                    | Build CONFIGxx member                        | To build a CONFIGxx member for the system from the definitions in the accessed IODF.                                                       |
| <b>p</b>                    | Process DISPLAY M=CONFIG(xx) command         | To compare the definitions in the CONFIGxx member with the hardware configuration of the system and display any results in a message list. |

---

## Commands

All HCD list panels have a command line, on which you can enter the usual ISPF commands and specific HCD commands.

You can get a list of available HCD commands by moving the cursor to the command line and pressing the F1=Help key.

As a fastpath to information about a specific HCD command, type the command before pressing the F1=Help key.

Some commands are described in the following table.

**Note:** On the help panel command line, only the help commands are available.

| Command                                          | Meaning                                                                                                                                                                                                                                                                       |
|--------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>GOto listtype</b><br><b>[parent objectid]</b> | Is a fastpath for going to another target panel without having to navigate through the dialog. You can specify the object (parent) with which some targets might be associated (esoterics associated with EDT and OS) and the object id of the first element in a list panel. |
| <b>GOto CHPID</b>                                | Channel path list                                                                                                                                                                                                                                                             |
| <b>GOto CONS</b>                                 | Console list                                                                                                                                                                                                                                                                  |
| <b>GOto CU</b>                                   | Control unit list                                                                                                                                                                                                                                                             |
| <b>GOto DEV</b>                                  | Device list                                                                                                                                                                                                                                                                   |
| <b>GOto EDT</b>                                  | EDT list                                                                                                                                                                                                                                                                      |
| <b>GOto ESO</b>                                  | Esoteric list                                                                                                                                                                                                                                                                 |
| <b>GOto GEN</b>                                  | Generic list                                                                                                                                                                                                                                                                  |
| <b>GOto MIG</b>                                  | Migrate configuration data                                                                                                                                                                                                                                                    |
| <b>GOto OS</b>                                   | OS configuration list                                                                                                                                                                                                                                                         |
| <b>GOto PART</b>                                 | Partition list                                                                                                                                                                                                                                                                |
| <b>GOto PORT</b>                                 | Port list                                                                                                                                                                                                                                                                     |
| <b>GOto PR</b>                                   | Processor list                                                                                                                                                                                                                                                                |
| <b>GOto SW</b>                                   | Switch list                                                                                                                                                                                                                                                                   |
| <b>GOto SWCON</b>                                | Switch Configuration                                                                                                                                                                                                                                                          |
| <b>GOto MATRIX</b>                               | Port Matrix                                                                                                                                                                                                                                                                   |
| <b>GOto X</b>                                    | Leave HCD dialog                                                                                                                                                                                                                                                              |
| <b>LEFT</b>                                      | Left or Hleft; scroll left on screen (= F19).                                                                                                                                                                                                                                 |
| <b>RIGHT</b>                                     | Right or Hright; scroll right on screen (= F20).                                                                                                                                                                                                                              |
| <b>INSTRUCT</b>                                  | View information about interaction (= F13), available only on panels containing the F13 key.                                                                                                                                                                                  |
| <b>Locate objectid</b>                           | Search for an object in an action list starting with the objectid characters.                                                                                                                                                                                                 |
| <b>SAVE</b>                                      | Saves list data into a data set, which then can be used for printing.                                                                                                                                                                                                         |
| <b>FIND port1 port2</b>                          | Search vertically, as well as horizontally, for a specific port intersection in the port matrix (on the Port Matrix panel only).                                                                                                                                              |
| <b>TRace [ON/OFF]</b>                            | Activate or deactivate HCD internal tracing.<br><br>For the syntax of this command refer to <i>z/OS HCD User's Guide</i>                                                                                                                                                      |
| <b>HELPID</b>                                    | Display panel ID (on help panels only).                                                                                                                                                                                                                                       |
| <b>SHOWMsg</b><br><b>[ACTivate]</b>              | Display the messages that are currently queued in the HCD message log. For messages issued during last activation request only, enter the activate parameter.                                                                                                                 |

**Command**  
**SHOWIodf**

**Meaning**  
Displays information about the currently  
accessed IODF data set.

---

## Online Help


- The F1=Help key with the cursor on an input field (or when a message is displayed) gives you **contextual field help** (or message help).
- The F1/F2=Ex\_help key from any contextual field help gives you Extended Help explaining the whole panel. (You get Extended help as well using **Help** from the action bar.)
- The F13=Instruct key, from an action list panel, provides Instruction help.
- The F1=Help or F9=Keys key, in a help window, gives you general information.
- The Enter key, with the cursor on a **Reference Phrase**, gives you more help. Reference phrases are highlighted HCD-specific terms, abbreviations or acronyms.

---

## How to Use the Dialog Efficiently

You can use the dialog efficiently with the display of positional information, by direct editing, by using keyboard and function keys, and prompts.

## Display Positional Information



The screenshot shows a dialog box with a rounded top and bottom. At the top, there are four menu items: "Goto", "Backup", "Query", and "Help". Below these is a dashed horizontal line. Underneath the line, the text "Row 20 of 158 More: < >" is displayed.

For example, Row 20 of 158 More: < >.

- Row 20 of 158 specifies that the first row of data that is displayed in the work area is the twentieth row of the 158 available rows.
- More: > specifies that more data can be seen by scrolling the work area to the right.
- More: < specifies that more data can be seen by scrolling the work area to the left.
- More: < > specifies that more data can be seen by scrolling the work area to the left as well as to the right.

## Direct Editing

When HCD asks you to specify some data, type the data in the appropriate entry field. The field might already contain data that you have previously defined or a default value inserted by HCD; you can overwrite this. Configuration data for an object can also be modified by overwriting the data on action list panel.

## Keyboard and Function Keys

HCD assumes that the terminal supports 24 function keys. If this is not so, HCD commands can be used for the functions that are assigned to keys F13 to F24, such as F13=Instruct, F19=Left, or F20=Right.

## Prompt

Whenever you see a + to the right of a field or on top of a column, HCD offers a prompt. Just press the F4=Prompt key and you get a list of valid values to choose from. Move the cursor on the choice you want and press the Enter key.

Prompt for action codes is available for the action entry field on action lists, although + is not shown. Requesting prompt for action codes displays the same context menu as when selecting an object and pressing the Enter key.





Printed in the United States of America  
on recycled paper containing 10%  
recovered post-consumer fiber.

SX33-9032-00

