

ADAINV Error Messages

Overview of Messages

ERROR-121 | ERROR-122 | ERROR-123 | ERROR-124 | ERROR-125 | ERROR-126 |
ERROR-127 | ERROR-128 | ERROR-129 | ERROR-130 | ERROR-131

ERROR-121 INVALID DESCRIPTOR FIELD LIST FOR INVERT

Explanation: The field name "xx" is either

- not found in the FDT; or
- already a descriptor.

Action: Supply the correct parameter value and rerun the job.

ERROR-122 TEMP DATASET TOO SMALL; INPUT RECORD COUNT= count

Action: Supply a larger TEMP dataset/file. See the Adabas Utilities documentation for information about calculating TEMP space.

ERROR-123 INVALID OR MISSING COUPLE DESCRIPTOR

Explanation: One of the supplied descriptor names

- is not supplied;
- is not found in the FDT;
- is not a descriptor;
- is a descriptor contained in a periodic group; or
- has a format/length that is incompatible with the other descriptor.

Action: Supply the correct parameter value and rerun the job.

ERROR-124 COUPLE INDEX OVERFLOW FOR FILE file-number

Explanation: This file is already coupled to 18 others; this is the maximum.

ERROR-125 FILES ALREADY COUPLED

Explanation: Utility function cannot be processed.

ERROR-126 COUPLING NOT POSSIBLE

Explanation: This error occurred because

- a file cannot be coupled to itself;
- expanded files cannot be coupled;
- multicient files cannot be coupled; and
- only file numbers less than 255 can be coupled.

The ADAINV function cannot be processed.

ERROR-127 MISSING UTILITY FUNCTION

Explanation: INVERT or COUPLE must be entered, then rerun ADAINV.

ERROR-128 INVALID VALUE FOR THE PARAMETER 'CODE'

Explanation: The value specified for the CODE parameter is either incorrect, or the CODE parameter is not valid in this case.

Action: Either remove the CODE parameter, or specify at most eight digits, or blanks. Rerun the job. Refer to the Adabas Security documentation for more information.

ERROR-129 AN ATTEMPT WAS MADE TO CREATE A 16TH INDEX LEVEL

Explanation: No more than 15 index levels are possible.

Action: Try this function again with a smaller value for ASSOPFAC.

ERROR-130 ERROR INITIALIZING COLLATING USER EXIT - RETURN CODE=return-code

Explanation: An error occurred while the collation descriptor user exit was being initialized.

Action: Investigate the cause of the error; correct it; and rerun the job.

ERROR-131 COLLATING USER EXIT NOT LOADED

Explanation: The collation descriptor user exit requested is not loaded.

Action: Load the exit and rerun the job.

