

Modifying an Active Report

Modifying General Attributes

▶ To modify the General Attributes of an Active Report

- On the Active Report List or Active Report List >Folder screen, enter MO in the two-character Cmd field preceding the appropriate Active Report and press Enter.

Active Report>General Attributes

```

13:19:41          **** ENTIRE OUTPUT MANAGEMENT ****          2002-10-10
User ID UKSJU      - Active Report>General Attributes -

Report
Name ..... UKSJU-XML2
Run number ..... 32530
Description .....
Location ..... S
Style.. FILE://EOM/NOM221U/SJUXSLT
Keywords .....
Master Owner ..... UKSJU__

Retention          Contents
Number ..... 5__   Number of Lines ... 1004
Factor ..... A     CC Type .....
Calendar .....    Record Length ..... 133
Action ..... P

Expiration Date ..... 2002-10-15

Command =>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Flip          Archv Reviv Spool      Menu
    
```

This screen displays the General Attributes for the Active Report, which are initialized during Report creation according to the rules defined in the respective Report definition. For further information, see the subsection General Attributes under the heading Adding a Report Definition.

Special PF Keys

PF Key	Function	Explanation
PF8	Archv	See Display/Modify Archive Attributes for Active Report.
PF9	Reviv	See Display/Modify Revive Attributes for Active Report.
PF10	Spool	See Display Spool Attributes for Active Report.

Field Descriptions

Report

- **Name** (not modifiable)
The Report name.
- **Run number** (not modifiable)
Internal sequence number of the Active Report.
- **Description** (not modifiable)
Short description of the Report.
- **Location** (not modifiable)
This is the location flag. It indicates the current storage location for the Active Report as described for the column heading L.
- **Style**
URL of an XML stylesheet is shown here, if defined. It cannot be modified. For more information, see XML Printers.
- **Long records** (not modifiable)
If **Y** appears here, it means that the report contains long records. For reports containing long records, number of lines is actually the number of segments and record length is actually the length of a segment.
- **Keywords**
Enter up to 3 keywords which will later help you select Reports.
- **Master Owner**
The Monitor takes the User ID of the Master Owner to submit print jobs for Reports to be scheduled for automatic printing. This field is initialized with the User ID of the person who defined the Report. You can enter a different User ID.

Retention

You can modify the four Retention fields. For an explanation, see the field descriptions under Retention / Report.

Contents

- **Number of Lines** (not modifiable)
Number of lines contained in the Active Report.
- **CC Type** (not modifiable)
Either ASA or MACHINE.
- **Record Length** (not modifiable)
Maximum number of bytes in record.
- **Expiration Date**
The contents of the Active Report are available online until this date.

List Active Report using Selected Keyword

To list active reports archived in a folder using a selected keyword

1. Enter the line command **LK** in the Active Reports >Folder Maintenance screen before the corresponding folder and press Enter.

The Keyword Input windows appears:

```

16:10:28          **** ENTIRE OUTPUT MANAGEMENT ****          2000-11-15
User ID GHH      - Active Reports>Folder Maintenance -

Cmd Folder      Description
-----
#Inbasket
LK Documents    Explains the structure of the individual documents
-----
+-----+
!           - Keyword input -           !
!                                           !
! Keyword: _____ !
!                                           !
!           PF3 Exit           !
+-----+
-----
-----
-----
-----
-----
-----
-----
-----
-----
-----
All
Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Add   Exit  Flip           -       +                   Reset Menu
    
```

2. Enter a particular keyword to list active reports to which this keyword is assigned.

OR

3. Enter a prefix ending with * to list the active reports to which the keyword with prefix entered is assigned.

The Active Reports screen appears in the defined layout (as specified in the Field Descriptions: Folder Definition >General Attributes in the field List Layout).

Modify Archive Attribute of Active Report

 **To modify the Archive Attributes of an Active Report**

- After invoking the Active Report >General Attributes screen with the MO line command, press PF8 (Archv).

The Active Report >Archive Attributes screen appears:

```

19:56:31          **** ENTIRE OUTPUT MANAGEMENT ****          2002-08-13
User ID UKSJU      - Active Report>Archive Attributes -

Report
  Name ..... UKSJU-ARCTYPE-03
  Run number ..... 31481

Retention
  Number ..... _____
  Unit ..... -

Archive
  Date ..... 2002-08-13
  Time ..... 16:26:36
  Expiration ..... 2002-09-02
  Expiration Orig. ..
  Type ..... 3
  Data set ..... RDU.SJU.NOMUDA3.NOM0371
  Volser(s) ..... UK0011

Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Flip                               Ext      Menu

```

This screen displays the Archive Attributes for the Active Report, which are initialized during Report creation according to the rules defined in the respective Report definition.

If you invoked the Active Report >General Attributes screen with the DI line command, you cannot modify any fields on this screen.

Field Descriptions

Report

As for General Attributes; see Field Descriptions: Active Report - General Attributes.

Retention

This is the length of time the Active Report is to be kept in the Archive. When this period expires, the Active Report is deleted from the Archive Data Set. An Active Report can be archived no matter where it is stored.

You can modify the Number and Unit fields, if the Active Report has not already been archived. For an explanation, see the field descriptions under Retention / Archive.

Archive

- **Date/Time** (not modifiable)
The date and time the Active Report was archived.
- **Expiration** (not modifiable)
Expiration date. The Active Report is retained in the archive until this date.
- **Expiration Orig.** (not modifiable)
Original expiration date.
If the Expiration Date has been modified, the original date appears here.
- **Type**
If archive is user-defined, the type number is shown here.
- **Data set** (not modifiable)
The name of the data set to which the Active Report was archived.

- **Volser (s)** (not modifiable)
The VOLSER of the archive containing the Active Report.

Modify Active Report Revive Attributes

▶ To modify the Revive Attributes of an Active Report

- After invoking the Active Report >General Attributes screen with the MO line command, press PF9 (Reviv).

The Active Report >Revive Attributes screen appears:

```

14:49:31          **** ENTIRE OUTPUT MANAGEMENT ****          2000-11-15
User ID MRS      - Active Report>Revive Attributes -

Report
  Name ..... ADABAS-START-JOB
  Run number ..... 21572

Retention
  Number ..... ____
  Unit ..... -
  Calendar ..... _____

Revive
  Date .....
  Time .....
  Expiration ..... _____

Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Flip                               Ext      Menu
    
```

This screen displays the Revive Attributes for the Active Report, which are initialized during Report creation according to the rules defined in the respective Report definition.

If you invoked the Active Report >General Attributes screen with the DI line command, you cannot modify any fields on this screen.

Field Descriptions

Report

As for General Attributes; see Field Descriptions: Active Report - General Attributes.

Retention

This is the length of time the contents of a revived Active Report are to be available online for browsing and printing. When this period expires, this 'copy' of the archived Report is purged automatically.

You can modify the Number, Unit and Calendar fields, if the Active Report has not already been revived. If the Active Report has been revived, you can modify the Expiration field below. For an explanation, see the field descriptions under Retention / Report.

Revive

- **Date**
The date the Active Report was revived.
- **Time**
The time the Active Report was revived.
- **Expiration**
The revived 'copy' of the Active Report contents is available until this date.
You can modify this field if the Active Report has already been revived.
If the Active Report has not been revived, you can modify the Number, Unit and Calendar fields above.

Display Active Report General Attributes

To display the General Attributes of an Active Report

- On the Active Report List or Active Report List >Folder screen, enter DI in the two-character Cmd field preceding the appropriate Active Report and press Enter.

The Active Report >General Attributes screen appears. With the display function, you can only view not modify the attributes.

Display Spool Attributes - POWER

To display the Spool Attributes of an Active Report

- On the Active Report List or Active Report List > Folder screen, enter SP in the two-character Cmd field preceding the appropriate active report and press Enter.

OR

- After invoking the Active Report >General Attributes screen with the DI or MO line command, press PF10 (Spool).

The Active Report >Spool Attributes screen appears:

```

14:50:25          **** ENTIRE OUTPUT MANAGEMENT ****          2000-11-15
User ID MRS      - Active Report>Spool Attributes -

Report
  Name ..... ADABAS-START-JOB
  Run number ..... 21572

Spool Type ..... POWER
Node ..... 33
Jobname ..... ADABAS
Jobnumber ..... 23354
Data set type ..... LS
Number of segments ... 1
FLASH .....
FORM .....
Copies ..... 1

Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Flip                               Ext      Menu
    
```

This screen displays the attributes of a POWER spool data set.

Field Descriptions

Report

As for General Attributes; see Field Descriptions: Active Report - General Attributes.

The remaining fields are attributes of the POWER spool data.

Display Spool Attributes - JES

To display the Spool Attributes of an Active Report (JES)

- After invoking the Active Report >General Attributes screen with the DI or MO line command, press PF10 (Spool).

The Active Report >Spool Attributes screen (JES) appears:

```

10:02:53          **** ENTIRE OUTPUT MANAGEMENT ****          2000-11-15
User ID MRS      - Active Reports>Spool Attributes -

Report
  Name ..... SCAN-'-RETENTIO
  Run number ..... 15285

Spool Type ..... JES          BURST .....
Node ..... 144              UCS .....
Jobname ..... GWSCAN        FCB .....
Jobnumber ..... 3788        FLASH .....
Data set type ..... SO      FORMS ..... STD
Data set ..... 1           FORMDEF .....
Data set key ..... 101      PAGEDEF .....
Group ID ..... 1.0001.0001  TRC ..... NO
Procname .....             COMPACT .....
Stepname ..... CUPOSCAN     LINECT .....
DDName ..... SYSPRINT       RECFM ..... FA
CHARS .....                Copies ..... 1

Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Flip                      Ext      Menu
    
```

This screen displays the attributes of a JES spool data set.

Field Descriptions

Report

As for General Attributes; see Field Descriptions: Active Report - General Attributes.

The remaining fields are attributes of the JES spool data. For more information, see the appropriate IBM reference manual.

Display Spool Attributes - NAF

To display the Spool Attributes of an Active Report (NAF)

- After invoking the Active Report >General Attributes screen with the DI or MO line command, press PF10 (Spool).

The Active Report >Spool Attributes screen (NAF) appears:

```

10:14:53          **** ENTIRE OUTPUT MANAGEMENT ****          2000-11-15
User ID MRS      - Active Report>Spool Attributes -

Report
  Name ..... DEPTBS1-0000
  Run number ..... 15589

Spool Type ..... NAF          Creation Date ..... 19990118
DBID ..... 10          Creation Time ..... 1013474
FNR ..... 60
User ID ..... MK1
NATURAL Library ..... NOM132
NATURAL Program ..... UEXEMPL9
Printer profile name . NOMPRT01
Logical destination .. 4 (1-31)
Form .....
Report name .....
Copies ..... 1
Disposition ..... H

Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Flip          Ext          Menu
    
```

This screen displays the attributes of a NAF spool data set.

Field Descriptions

Report

As for General Attributes; see Field Descriptions: Active Report - General Attributes.

The remaining fields are attributes of the NAF spool data.

Display Spool Attributes - BS2000/OSD

To display the Spool Attributes of an Active Report (BS2000/OSD)

- After invoking the Active Report >General Attributes screen with the DI or MO line command, press PF10 (Spool).

The Active Report >Spool Attributes screen (BS2000/OSD) appears:

```

16:37:40          **** ENTIRE OUTPUT MANAGEMENT ****          2000-11-15
User ID NOM      - Active Report>Spool Attributes -

Report
  Name ..... DEPTDS1-VENT
  Run number ..... 12348

Spool Type ..... BS2000/OSD
Node ..... 31          Rotation .....
Job name ..... NOMSTD1      Dia .....
User ID ..... NOM          Copies .....
Job ID ..... 1SM0          Form ..... STD
Originator Job ID .... 1SMZ      Control ..... NO
Destination ..... DRGW1      Chars .....
Device ..... DRGW1

Recform ..... F M          Size ..... 195
Reclsize ..... 133          Secondary ..... 96
Blocksize ..... 6144
Data set ..... $NOM.MRS.LST.EMPLOYEES.0000000913

Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Flip  Do    Undo          Ext      Menu
    
```

This screen displays the attributes of a BS2000/OSD print file and the parameters of the BS2000/OSD print command.

Field Descriptions

Report

As for General Attributes; see Field Descriptions: Active Report - General Attributes.

The remaining fields are attributes of the BS2000/OSD print file.

Display Spool Attributes - CMA-SPOOL

To display the Spool Attributes of an Active Report (CMA-SPOOL)

- After invoking the Active Report >General Attributes screen with the DI or MO line command, press PF10 (Spool).

The Active Report >Spool Attributes screen (CMA-SPOOL) appears:

```

16:38:40          **** ENTIRE OUTPUT MANAGEMENT ****          2000-11-15
User ID          - Active Reports>Spool Attributes -

Report
  Name .....
  Run number .....

Spool Type ..... CMASPOOL          Fcb .....
File sequence number .          Prmode .....
File name .....          Formdef .....
User ID .....          Pagedef .....
Account number .....          Chars .....
Programmers name .....          Writer .....
Room .....          Destination .....
System ID .....          Class .....
Linect .....          Lines .....
Retain .....          Pages .....
Forms .....          Priority .....
Trc .....          Copies .....
Compression .....

Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Flip  Do    Undo          Ext      Menu
    
```

This screen displays the attributes of a CMA-SPOOL data set.

Field Descriptions

Report

As for General Attributes; see Field Descriptions: Active Report - General Attributes.

The remaining fields are attributes of the CMA-SPOOL data.

Display Spool Attributes - SAP

To display the Spool Attributes of an Active Report (SAP)

- After invoking the Active Report >General Attributes screen with the DI or MO line command, press PF10 (Spool).

The Active Report >Spool Attributes screen (SAP) appears:

```

09:58:10          **** ENTIRE OUTPUT MANAGEMENT ****          2000-11-15
User ID GHH      - Active Reports>Spool Attributes -

Report
  Name ..... A-SAP-TEST1
  Run number ..... 25759

Spool Type ..... SAP-Spool

Destination ..... L334
List ID ..... LISTEN
User ID ..... MOSE
Task ID ..... B803

Formdef .....
Pagedef .....

Chars .....
Copies ..... 00

Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Flip  Do    Undo          Ext          Menu
    
```

This screen displays the attributes of an SAP spool data set.

Field Descriptions

Report

As for General Attributes; see Field Descriptions: Active Report - General Attributes.

The remaining fields are attributes of the SAP spool data.

Display Spool Attributes - 3GL Interface

To display the Spool Attributes of an Active Report (3GL Interface)

- After invoking the Active Report >General Attributes screen with the DI or MO line command, press PF10 (Spool).

The Active Report >Spool Attributes screen (3GL Interface) appears:

```

10:47:41          **** ENTIRE OUTPUT MANAGEMENT ****          2000-11-15
User ID GHH          - Active Reports>Spool Attributes -

Report
  Name ..... USR104-TEST
  Run number ..... 26657

Spool Type ..... 3GL Interface 104
User ID ..... USERID..
Terminal ID ..... TERMID..
Program ..... PROGID..
List-Name ..... LISTNAM.
List ID ..... LISTID..
Description ..... DESCRIPT

All
Command => _____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit Flip Do      Undo -      +      Ext      Menu
    
```

This screen displays the attributes of a 3GL Interface spool data set.

Field Descriptions

Report

As for General Attributes; see Field Descriptions: Active Report - General Attributes.

The remaining fields are attributes of the 3GL Interface spool data.