

# Messages and Codes - EOR0401 - EOR0600

This subsection covers the following topics:

- Displaying a Long Message Text
- Messages EOR0401 - EOR0600 in Numerical Order

## Displaying a Long Message Text

▶ To display a long message text

- Use the direct command

**HELP MSG <message-code>**

## Messages EOR0401 - EOR0600 in Numerical Order

Message	Explanation	Action
<b>EOR0401 - Invalid BS2000 File Name::1:</b>	The format of a BS2000 file name is not valid for the operating system file name syntax. :1: contains the reason.	
<b>EOR0402 - Invalid BS2000 User ID</b>	1. The User ID is not defined in BS2000. 2. The User ID TSOS may be defined only if the user is currently working under TSOS. 3. The User ID must not start with '\$'.	Enter a valid BS2000 User ID.
<b>EOR0403 - Invalid Pubid,:1:</b>	A BS2000 file name has a wrong syntax.	
<b>EOR0404 - Invalid User ID,:1:</b>	A BS2000 file name has a wrong syntax.	
<b>EOR0405 - Invalid Name,:1:</b>	A BS2000 file name has a wrong syntax.	
<b>EOR0406 - Default User ID added to File Name</b>	The BS2000 file name did not contain a BS2000 user ID. The file name was completed with the default job or network BS2000 userid.	
<b>EOR0411 - Invalid User Switch Value</b>	A BS2000 user switch may have a value from 0 thru 31.	Correct error.
<b>EOR0421 - Invalid Substring Position</b>	The position of a Job Variable substring must be in the range 1 - 253 (BS2000).	
<b>EOR0422 - Invalid Substring Length</b>	The maximum length of a Job Variable substring is 253 (BS2000).	
<b>EOR0423 - Substring position and length not evaluated</b>	With formats D (Date) and N (Numeric), the values of substring position and substring length are not considered. Thus, you cannot compare a date or a numeric string partially with a given value.	

<b>EOR0429 - Job Variables not available on Node:1:</b>	The BS2000 Software Product 'Job Variables' has not been installed on this BS2000 system. The 'Job Variable' functions of Entire Operations can therefore not be used.	
<b>EOR0440 - Invalid Member Type</b>	The function requires a valid member type.	
<b>EOR0441 - Invalid Member Name</b>	The member name contains at least one character which is invalid for the location naming conventions.	
<b>EOR0442 - Member Type not allowed for:1:</b>	The member type may be specified for some JCL locations, such as LMS (BS2000), and VSE.	Delete field, or use another JCL location.
<b>EOR0450 - Job-Class must start with a character</b>	The Job-Class must start with a character. Exceptions are: Blank or '*STD'. Applies for BS2000 only.	Correct error.
<b>EOR0461 - BS2000 'not ok' codes::1:</b>	A BS2000 job will be treated as not ok by default, if any of these message codes appears in the job sysout.	
<b>EOR0462 - BS2000 'not ok' codes: none defined</b>	The table of BS2000 'not ok' message codes is empty.	
<b>EOR0471 -:1:- No access to BS2000 User ID:2:</b>	The access to a BS2000 User ID is denied for this user.	
<b>EOR0481 - User ID too long (max. 8 chars.)</b>	It is not possible to define a user ID longer than 8 characters for this operating system.	
<b>EOR0482 - Group too long (max. 8 chars.)</b>	It is not possible to define a group longer than 8 characters for this operating system.	
<b>EOR0501 - Volume obligatory for DOS/VSE</b>	The JCL location VSE requires an obligatory volume definition.	
<b>EOR0502 - Library/Sublib not found</b>	The defined VSE library or sublibrary does not exist.	Correct definition, or use a wildcard ('*') for a sublibrary selection.
<b>EOR0503 - Invalid File Type. (Use RDR,LST,PUN,XMT.)</b>		Enter a valid VSE file type.
<b>EOR0504 - No unique member selected from VSE/POWER RDR</b>		
<b>EOR0505 - JOB card invalid or omitted</b>		
<b>EOR0506 - STC is currently active</b>		
<b>EOR0507 - Default Member Type inserted</b>	The member type was taken from the Entire Operations Defaults.	
<b>EOR0508 - Recfm, Lrecl, Blksize obligatory for VSE</b>	These fields must be specified for VSE.	
<b>EOR0520 - Library.Sublib invalid</b>	Library and sublibrary must be specified concatenated, with a separating '.' The length of each must not exceed 8 characters.	Enter a valid library.sublib definition.

<p><b>EOR0521 - Member.Type invalid</b></p>	<p>Member and member type must be specified concatenated, with a separating '.' The length of each must not exceed 8 characters.</p>	<p>Enter a valid member-type definition.</p>
---	--	--