

TF - Translation of Database ID/File Number

This Natural profile parameter is for:

- mainframes
- UNIX and Windows



The parameter TF applies to user files only, **not** to system files.

Mainframes

This parameter can be used to translate a database ID/file number to another database ID/file number during the execution of an application. It can be used to dynamically specify the same values which can be specified statically with the macro NTTF in the parameter module.

Possible settings	<i>production-DBID</i>	Must be in the range of 0 to 254, or 256 to 65535, or can be "*" which stands for all DBIDs.
	<i>production-FNR</i>	Must be in the range of 1 to 65535, or "*" which stands for all FNRs.
	<i>test-DBID</i>	Must be in the range of 0 to 254, or 256 to 65535, or can be "*" which leaves the DBID unchanged.
	<i>test-FNR</i>	Must be in the range of 1 to 65535, or "*" which leaves the DBID unchanged.
Default setting	none	
Dynamic specification	YES	This parameter can only be specified dynamically. In the Natural parameter module, the macro NTTF must be used instead.
Specification within session	NO	

This feature is relevant when developing an application in a production environment. It enables you to develop an application in a test database and then transfer the finished application to the production database without having to change or re-compile the application. The Natural objects are cataloged with the production DBID/FNR, but whenever a database access is executed, the production DBID/FNR is translated into the test DBID/FNR according to the TF parameter specifications; that is, the test database is used. This means that testing can take place in the actual production environment, but not with production data.

The TF parameter or the NTTF macro can be specified several times so as to specify different combinations of file numbers.

The following topics are covered below:

- TF Parameter Syntax
- NTTF Macro Syntax
- Example of TF Parameter
- Example of NTTF Macro

TF Parameter Syntax

The TF parameter is specified as follows:

```
TF=(production-DBID,production-FNR,test-DBID,test-FNR)
```

NTTF Macro Syntax

The NTTF macro is specified as follows:

```
NTTF production-DBID,production-FNR,test-DBID,test-FNR
```

Example of TF Parameter

```
TF=(777,39,17,88),TF=(251,*,9,*)
```

Example of NTTF Macro

Equivalent specification in the Natural parameter module:

```
NTTF 777,39,17,88
NTTF 251,*,9,*
```

UNIX and Windows

This parameter is used to translate the database ID/file number of a production database into the database ID/file number of a test database.

Possible settings	see text "*" for production DBID and FNR
Default setting	none
Dynamic specification	YES
Specification within session	NO

The TF parameter can be specified several times. Existing specifications are displayed in a corresponding list box.

Note:

Production and test databases must be of the same type (Adabas/Adabas, for example).

Note:

For SQL databases, the file number must always be set to 1.