

Object Handler Wizards

The Object Handler provides wizards that determine the processing sequence for

- Unloading data from the Natural system environment into Natural work files.
- Loading data from work files into the Natural system environment.
- Scanning the contents of Natural work files.

To activate the wizards

- On the Natural Object Handler Main Menu, select the "Advanced user" field if required (the field is not selected by default).

The wizards provide the keys PF8 and PF7 to navigate between the screens (steps). Use PF12 to cancel the processing sequence.

The steps below describe the processing sequence performed with the unload, load or scan wizard:

- Step 1 - Start the Procedure
 - Step 2 - Unload/Load/Scan Object into/from Work Files
 - Step 3 - Set Parameters
 - Step 4 - Select Objects
 - Step 5 - Execute Processing
 - Step 6 - Continue Processing
-

Step 1 - Start the Procedure

To start the unload, load or scan procedure

1. From the Natural Object Handler Main Menu, choose Unload, Load or Scan by entering any single character next to the function desired or by using the corresponding PF key.
The Unload/Load/Scan Wizard main screen appears with the following options:
 1. Unload/Load/Scan objects into/from Natural work file(s)
 2. Start Object Handler command procedure
2. Choose any option:
 - If you choose "Unload/Load/Scan objects into/from Natural work file(s)", proceed with Step 2 below.
 - If you choose "Start Object Handler command procedure", proceed as follows:
 1. On the Unload/Load/Scan Wizard screen, choose "Start Object Handler command procedure".
The Procedure screen appears.
 2. In the Name field, enter the name of a Workplan of the type PROCEDURE by using either option below:
 - Type in the name of a Workplan of the type PROCEDURE (see also Workplans) that should be used for the transaction.
 - Choose Select Workplan or choose PF5 to display a list of available Workplans of the type PROCEDURE.
In the line next to the Workplan you want to select, enter the command **S** or **SE**.
Press ENTER to execute the command and fill the Name field on the Procedure screen.
 3. Select List Workplan or choose PF4 if you want to display the Workplan specified.

See also List Workplan in the section Administration.

3. Press ENTER to continue.
4. Proceed with Step 5 and Step 6 below.

Step 2 - Unload/Load/Scan Objects into/from Work Files

To unload, load or scan objects into/from Natural work files

1. On the Unload/Load/Scan Wizard screen, choose "Unload/Load/Scan objects into/from Natural work file(s)".
2. Press ENTER or choose PF8/Next to continue.

The Options screen of the wizard appears with the following fields, commands and alternative PF keys:

Field	PF Key	Explanation
Transfer format		<p>Only valid if "Use default options" (this is the default) has been selected.</p> <p>If selected, the data to be processed is written in Transfer format into/from the work file. See also Work File Format in the section Work Files.</p> <p>Unload function: The data to be unloaded is written in Transfer format into the work file. Note that if you want to change the setting of this field for a subsequent unload, you need to return to the Natural Object Handler Main Menu or enter the command GO UNLOAD END (see Commands for CUIs) and restart the unload function.</p> <p>Load and scan functions: The data to be loaded or scanned are expected to be in Transfer format.</p>
Use PC work file		<p>Only applies if Entire Connection is installed.</p> <p>If selected, the data to be processed is written into an Entire Connection work file.</p>
PC File		<p>Only valid if "Use PC work file" has been selected.</p> <p>The name of the path and the Entire Connection work file to be used.</p>
Use default options		<p>Default options are (this is the default). For the options available, see SYSOBJH Profile and Set Additional Options in the section Settings.</p>
Set additional options	PF4	<p>Only valid if "Use default options" has been selected.</p> <p>Invokes the Options screen of the wizard where you can modify the default settings and enter additional options for the processing sequence. See Set Additional Options in the section Settings.</p>
Use Option Workplan		<p>If selected, a Workplan of the type OPTION is used (see Workplans).</p>
Name		<p>Only valid if Use Option Workplan has been selected.</p> <p>The name of a Workplan of the type OPTION to be used.</p>
List Option Workplan	PF6	<p>Only valid if Use Option Workplan has been selected.</p> <p>Displays the contents of the Workplan specified in the field Name.</p>
Select Option Workplan	PF5	<p>Only valid if Use Option Workplan has been selected.</p> <p>Displays a selection list of available Workplans of the type OPTION (see also List Workplan in the section Administration).</p>

3. Select any of the options provided and (if necessary) complete the fields to be used for the processing sequence.
4. Press ENTER or choose PF8/Next to continue.
The Parameters screen of the wizard appears.

Step 3 - Set Parameters

To set parameters for the processing procedure

1. On the Parameters screen, select any of the following options listed below and (if necessary) complete the fields to be used for the processing sequence:

Field	PF Key	Explanation
Do not use parameters		If selected (default), no parameters are set.
Use global parameters		If selected, global parameters are used. See Set Global Parameters in the section Settings.
Set global parameters	PF4	Only valid if "Use global parameters" has been selected. If selected, the Parameters screen is invoked. See Set Global Parameters (Settings) and Parameter-Setting (Direct and PROCEDURE Workplan Syntax, Commands) for a description of keywords and valid values.
Use Parameter Workplan		If selected, a Workplan of the type PARAMETER is used (see Workplans).
Name		Only valid if Use Parameter Workplan has been selected. The name of a Workplan of the type PARAMETER to be used.
List Parameter Workplan	PF6	Only valid if Use Parameter Workplan has been selected. If selected, the contents of the Workplan specified in the field Name is displayed.
Select Parameter Workplan	PF5	Only valid if the field Use Parameter Workplan has been selected. If selected, a selection list of available Workplans of the type PARAMETER is displayed (see List Workplan in the section Administration).

2. Press ENTER or PF8/Next to continue.
The Select Unload/Load/Scan Type screen appears.

Step 4 - Select Objects

To select the type of object you want to process

- On the Select Unload/Load/Scan Type screen, use any of the three options below. Note that the first option only applies to the load and scan functions. For the keywords and valid values that apply to each object type, see the relevant explanation in the section Object Specification.
 1. Select "Load/Scan all objects" to process all objects from the work file.
 2. Select a particular type of object:
 - Natural library objects
 - Natural system error messages
 - Natural command processor sources
 - Natural-related objects

- DDMs
- FDTs

Press ENTER or choose PF8/Next to continue.

Depending on the type of object selected, a screen appears where you can specify selection criteria for the objects to be processed.

Specify the objects and choose Details (if available) for further object specification, if required. For information on Details, see the relevant explanation in the section Object Specification.

3. Select "Use Selection or List Workplan" to use a Workplan of the type SELECTION or LIST. See also Workplans.

Press ENTER or choose PF8/Next to continue.

The Selection or List screen appears.

In the Name field, enter the name of a Workplan of the type SELECTION or LIST by using either option:

- Type in the name of a Workplan.
- Or, choose Select Workplan or PF5/SelWP to display a list of all Workplans available.
In the line next to the Workplan you want to select, enter the command **S** or **SE**. Press ENTER to execute the command and fill the Name field on the Selection or List screen. See also List Workplan in the section Administration.

Choose List Workplan or PF4/Li-WP if you want to display the contents of the Workplan entered in the Name field.

- Press ENTER or choose PF8/Next to continue.
The wizard displays the processing command generated from the input data.
You can save the command displayed as a Workplan of the type PROCEDURE (see also Workplans), by entering the command SAVE or by choosing PF5/Save.

Step 5 - Execute Processing

To execute the processing procedure

1. On the command execution screen, press ENTER or choose PF8/Next to confirm the settings and to process the objects specified.
If required, choose PF7/Back and modify the processing settings before you confirm the command execution.
The Object Handler performs the function and displays a confirmation message.
2. Press ENTER to continue.
A report screen appears with a list of the objects processed.
3. Choose PF3/Exit again to leave the report screen or choose PF12/Canc to terminate the function.
A window appears where you choose whether to continue processing data.
4. Choose No and press ENTER to terminate the function.
Or choose PF12 to terminate the function.

The Natural Object Handler Main Menu appears.

Step 6 - Continue Processing

To continue processing

1. On the report screen, choose PF3/Exit.
A window appears where you choose whether to proceed with the next processing step.

2. Choose Yes.

A screen appears with the option to reuse or change previous settings.