

SYSERR - Direct Commands

From the SYSERR main menu, you can execute the following commands by entering them in the Command line:

Command	Function
LAYOUT	Specifies valid message ranges to categorize messages. Overlapping of ranges is possible. A new message can only be added if its number is within the range specified in the layout.
NEXT	Searches for the next free message number within the message number range specified. Free means that this message number is available and has not yet been assigned to a message file in any language.
NEXTTAB	Same as NEXT, but returns a list of numbers from which you can select a certain number.
RESTART	Re-initializes SYSERR (and its default values) without leaving the utility.
SAMPLE	<p>Invokes the "Edit SAMPLE message" window where you create or modify a sample message to be used as a master for creating new short messages.</p> <p>To create or modify a sample message, proceed as follows:</p> <p>In the editor area of the "Edit SAMPLE message" window, type in the message text desired or modify existing text.</p> <p>If you enter the string 0000 (combined with text or not), the string 0000 is replaced by the number of the new message when copying the message. See also Copying a Sample Message in the section Functions.</p> <p>In the field "Read or Write sample", enter a W to save your entries.</p> <p>In the field Library, enter the name of the library for which the sample message is to be used. If you leave the field Library blank, the sample applies to Natural system messages.</p> <p>Press PF3 to exit the "Edit SAMPLE message" window.</p> <p>You can define one sample message for each language and library.</p>
SECURITY	Invokes a security window where you can enter a password and cipher code for accessing security-protected Adabas and VSAM files.
SHIFT	If activated, automatically shifts the text of a short message to the left margin when confirming a modification or adding a new message.
TRACE	Counts the number of database accesses. When the message number specified has been reached, a window is displayed. The default number is 900. If set to 0, the trace facility is shut off. The commands TRACE ON and TRACE OFF can be entered directly in the command line. TRACE ON sets the access counter to 900; TRACE OFF sets the access counter to 0.
USEREXIT	Invokes the program USEREXIT in the Natural system library SYSERR.