

Activate User Exits

Activate or deactivate user exits connected to different functions of Predict.

The Activate User Exits screens are displayed with function code U in the Defaults menu, or with the command DEFAULT EXIT.

| | | |
|------------------------------------|---------------------------------|--|
| 10:07:07 | ***** P R E D I C T 4.3.1 ***** | 2003-05-31 |
| - Activate User Exits - | | |
| --- User exits (subprograms) --- | | Modified 2003-05-31 at 09:21 by RBN |
| Maintenance | | Active retrieval |
| before any function .. N (Y/N) | | Y (Y/N) |
| add, copy, modify N (Y/N) | | N (Y/N) |
| purge, scratch N (Y/N) | | N (Y/N) |
| modify description ... N (Y/N) | | N (Y/N) |
| redocumentation N (Y/N) | | N (Y/N) |
| Retrieval | | File implementation |
| before any function .. N (Y/N) | | N (Y/N) |
| after display* N | | |
| Generation | | Comparison |
| before execution N (Y/N) | | N (Y/N) |
| after execution N (Y/N) | | N (Y/N) |
| Incorporation | | N (Y/N) |
| Administration | | N (Y/N) |
| Command processor | | N (Y/N) |
| Defaults/Special functions | | N (Y/N) |
| Check against naming conventions . | | N (Y/N) |

| | |
|---|------------------------------|
| ----- User exits (programs) ----- | Modified 2003-05-31 at 09:21 |
| | by RBN |
| ACM PURGE CAT | |
| Database N (Y/N) N (Y/N) | |
| Elementary field .. N (Y/N) N (Y/N) N (Y/N) | |
| File N (Y/N) N (Y/N) | |
| Keyword N (Y/N) N (Y/N) | |
| Program N (Y/N) N (Y/N) | |
| File relation N (Y/N) N (Y/N) | |
| System N (Y/N) N (Y/N) | |
| User N (Y/N) N (Y/N) | |
| Verification N (Y/N) N (Y/N) | |
| Owner* N | |
| For HELP enter '?' in the first input field. To leave enter '..' | |
| Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- | |
| Help Next Stop Last LnkEl Flip Print Impl AdmFi SelFi Prof Main | |

The tables below give an overview of how to activate user exits. A comprehensive description of all user exits including detailed information on how to activate them is contained in the section User Exits of this documentation.

Note:

The user exits U-MODEL and U-XREF are activated in the Metadata Administration. U-PGMLA, used to define new programming languages to Predict, is always active.

| Parameters (First Screen) | Activates User Exit(s) |
|----------------------------------|-------------------------------|
| Maintenance | |
| before any function | U-MNT and U-MNT1 |
| add, copy, modify | U-ACM and U-ACMR |
| purge, scratch | U-PUR |
| redocumentation | U-REDOC |
| modify description | U-DESC |
| Retrieval | |
| after display | U-DSP (option N, O and F) |
| before any function | U-RET |
| Generation | |
| before execution | U-GEN |
| after execution | U-GEN1 |
| Other | |
| Active retrieval | U-ACT |
| File implementation | U-IMPL |
| Comparison | U-COM |
| Incorporation | U-INC |
| Administration | U-MIP |
| Command Processor | U-CMD |
| Defaults/Special functions | U-SPEC |
| Check against naming conv. | U-OBJID |

| Parameters (Second Screen) | Activates User Exit(s) |
|-----------------------------------|---|
| Database | ACMDAEX, PURDAEX, CATDAEX |
| Field | ACMELEX, PURELEX, CATELEX |
| File | ACMFIEX, PURFIEX, CATFIEX |
| File Relation | ACMRLEX, PURRLEX, CATRLEX |
| Keyword | ACMKYEX, PURKYEX, CATKYEX |
| Program | ACMPREX, PURPREX, CATPREX |
| System | ACMSYEX, PURSYEX, CATSYEX |
| User | ACMUSEX, PURUSEX, CATUSEX |
| Verification | ACMVEEX, PURVEEX, CATVEEX |
| Owner | U-OW and CATOWEX (option N, Y, B and U) |

Overview of Activating User Exits

| User Exit | Activate with Parameter |
|------------------|---|
| U-ACM and U-ACMR | Parameter add, copy, modify |
| U-ACT | Parameter Active retrieval |
| U-AM-A | Parameter add, copy, modify |
| U-CMD | Parameter Command Processor |
| U-COM | Parameter Comparison |
| U-DESC | Parameter Maintenance / modify description |
| U-DSP | Parameter Retrieval / after display |
| U-GEN | Parameter Generation / before execution |
| U-GEN1 | Parameter Generation / after execution |
| U-IMPL | Parameter File implementation |
| U-INC | Parameter Incorporation |
| U-OBJID | Parameter add, copy, modify |
| U-MIP | Parameter Administration |
| U-MODEL | Parameter Userexits / U-MODEL in the Metadata Administration. See User exits. |
| U-MNT and U-MNT1 | Parameter Maintenance / before any function. |
| U-OW | Parameter Owner |
| U-PGMLAN | always active |
| U-PUR | Parameter Maintenance / purge, scratch |
| U-REDOC | Parameter Maintenance / redocumentation |
| U-RET | Parameter Retrieval / before any function |
| U-XREF | Parameter Userexits / U-XREF in the Metadata Administration. See User exits. |