

## Activate User Exits

Activate or deactivate user exits connected to different functions of Predict.

The Activate User Exits screens are displayed with function code U in the Defaults menu, or with the command DEFAULT EXIT.

```

10:07:07          ***** P R E D I C T 4.2.2      *****
                     - Activate User Exits -
  

--- User exits (subprograms) ---                         Modified 2002-07-31 at 13:21
  

by RBN
  

  

Maintenance
before any function .. N (Y/N)           Active retrieval ..... Y (Y/N)
add, copy, modify .... N (Y/N)           File implementation ..... N (Y/N)
purge, scratch ..... N (Y/N)            Comparison ..... N (Y/N)
modify description ... N (Y/N)          Incorporation ..... N (Y/N)
redocumentation ..... N (Y/N)          Administration ..... N (Y/N)
                                         Command processor ..... N (Y/N)
                                         Defaults/Special functions ..... N (Y/N)
                                         Check against naming conventions . N (Y/N)
  

Retrieval
before any function .. N (Y/N)
after display .....* N
  

Generation
before execution ..... N (Y/N)
after execution ..... N (Y/N)

```

```
----- User exits (programs) ----- Modified 2002-07-31 at 13:21
                                         by RBN

          ACM      PURGE      CAT

Database ..... N (Y/N)  N (Y/N)
Elementary field .. N (Y/N)  N (Y/N)  N (Y/N)
File ..... N (Y/N)  N (Y/N)
Keyword ..... N (Y/N)  N (Y/N)
Program ..... N (Y/N)  N (Y/N)
File relation ..... N (Y/N)  N (Y/N)
System ..... N (Y/N)  N (Y/N)
User ..... N (Y/N)  N (Y/N)
Verification ..... N (Y/N)  N (Y/N)
Owner .....*           N

For HELP enter '?' in the first input field. To leave enter '..'
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help Next Stop Last LnkEl Flip Print Impl AdmFi SelFi Prof Main
```

The tables below give an overview of how to activate user exits. A comprehensive description of all user exits including detailed information on how to activate them is contained in the section [User Exits](#) of this documentation.

Note:

The user exits U-MODEL and U-XREF are activated in the Metadata Administration. U-PGMLA, used to define new programming languages to Predict, is always active.

<b>Parameters (First Screen)</b>	<b>Activates User Exit(s)</b>
<b>Maintenance</b>	
before any function	U-MNT and U-MNT1
add, copy, modify	U-ACM and U-ACMR
purge, scratch	U-PUR
redocumentation	U-REDOC
modify description	U-DESC
<b>Retrieval</b>	
after display	U-DSP ( option N, O and F)
before any function	U-RET
<b>Generation</b>	
before execution	U-GEN
after execution	U-GEN1
<b>Other</b>	
Active retrieval	U-ACT
File implementation	U-IMPL
Comparison	U-COM
Incorporation	U-INC
Administration	U-MIP
Command Processor	U-CMD
Defaults/Special functions	U-SPEC
Check against naming conv.	U-OBJID

<b>Parameters (Second Screen)</b>	<b>Activates User Exit(s)</b>
Database	ACMDAEX, PURDAEX, CATDAEX
Field	ACMELEX, PURELEX, CATELEX
File	ACMFIEX, PURFIEX, CATFIEX
File Relation	ACMRLEX, PURRLEX, CATRLEX
Keyword	ACMKYEX, PURKYEX, CATKYEX
Program	ACMPREX, PURPREX, CATPREX
System	ACMSYEX, PURSYEX, CATSYEX
User	ACMUSEX, PURUSEX, CATUSEX
Verification	ACMVEEX, PURVEEX, CATVEEX
Owner	U-OW and CATOWEX (option N, Y, B and U)

## Overview of Activating User Exits

User Exit	Activate with Parameter
U-ACM and U-ACMR	Parameter add, copy, modify
U-ACT	Parameter Active retrieval
U-AM-A	Parameter add, copy, modify
U-CMD	Parameter Command Processor
U-COM	Parameter Comparison
U-DESC	Parameter Maintenance / modify description
U-DSP	Parameter Retrieval / after display
U-GEN	Parameter Generation / before execution
U-GEN1	Parameter Generation / after execution
U-IMPL	Parameter File implementation
U-INC	Parameter Incorporation
U-OBJID	Parameter add, copy, modify
U-MIP	Parameter Administration
U-MODEL	Parameter Userexits / U-MODEL in the Metadata Administration. See User exits.
U-MNT and U-MNT1	Parameter Maintenance / before any function.
U-OW	Parameter Owner
U-PGMLAN	always active
U-PUR	Parameter Maintenance / purge, scratch
U-REDOC	Parameter Maintenance / redocumentation
U-RET	Parameter Retrieval / before any function
U-XREF	Parameter Userexits / U-XREF in the Metadata Administration. See User exits.