

Display/Modify Master Symbol Table

This subsection covers the following topics:

- Modify Existing Master Symbol Table
- Column Headings
- Special PF Keys

Modify Existing Master Symbol Table

Modifying a master symbol table consists of adding, modifying or deleting symbols and their current values in an existing symbol table.

To modify an existing master symbol table

- Type **L** in the line command input field of the selected symbol table in the Master Symbol Tables window. Press Enter.

The Master Symbol Table screen appears: (You can also display this screen by pressing PF7 (Symb) from the Master Job Definition window).

```

11.11.01          *** Entire Operations 4.1.1 ***          15:59:08
Owner   SN          Master Symbol Table EXAM-ST1
Network                                     Run
-----
C Symbol          F P Value          modified by
_ CLASS          A E G              SN          05.02.00 12:32
_ HUGO           A E HUGO             SN          20.11.99 10:33
_ JOBLIB         A E EOR.DEV.LOAD         GHH         22.04.01 15:58
_ JOBNAME        A E SNE6201             SN          14.05.99 17:26
_ MSGCLASS       A E X                  SN          05.02.00 12:32
_ STEPLIB        A E EOR.DEV.LOAD         SN          11.03.00 08:40
_ TEST           A E TEST                 SN          20.11.99 10:32
_ UID            A E SN                  SN          05.02.00 12:31
-
-
-
-
-
-
***** Bottom of Data *****
C Copy   D Delete   M Modify
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Add     End       Save      Up      Down      Print
    
```

This window lists the symbols defined for the table by name, format, prompt value and current symbol value. Information is provided on the right concerning the user and date and time when the symbol was last modified.

You can add, modify and delete a symbol from the table.

Column Headings

Meaning of the column headings:

Column	Description	
C	One-character line command input field. Possible values:	
	C	Copy symbol.
	D	Delete symbol.
	M	Modify symbol.
Symbol Name	Name of the symbol used as variable.	
F	Format of the variable. Possible values:	
	A	Alphanumeric (including special characters)
	D	Date
	L	Alphanumeric; conversion to lower-case letters
	N	Numeric
	U	Alphanumeric; conversion to upper-case letters
P	Prompting. Is the user prompted for this symbol during manual activation of the job network? Possible values:	
	A	Prompted for symbol at each activation.
	E	Prompted only if no value is specified in table.
	N	Never prompted for symbol.
Value	Current value of the variable, i.e. the string or number substituted in dynamically generated JCL.	
	*** empty ***	Means the field is blank .
	*** ... multiple values ***	Means you must use the M line command to display the multiple values.
modified by	User who last modified the symbol followed by date and time of last modification.	

Special PF Keys

Key	Name	Function
PF10	Print	Print symbol table with all symbols on the printer assigned to PRINTER1. Exception for BS2000: An additional window opens in which you are asked to enter the printer name. If you wish to print via FORMS, because RSO is not installed, enter the following in the field Print Device: F=formname.