

Z-GET01

This chapter covers the following topics:

- Description
 - Parameters
 - Return Codes
 - Subprograms
-

Description

Return information about a nickname for an address at an external node or for an internal Con-nect address.

This subprogram does not apply to a transport service node. To return information about a nickname for a transport service node, you must use Z-GET01T.

The parameters Node-name, Node-parameters, Parameter-length and Post-flag only apply to an external address. They do not apply to an internal address.

This subprogram is generally used with Z-MOD01A to allow the modification of addressee information. The addressee information is then used by Z-MAILA for the distribution of mail.

Parameters

Parameter	Format	In	Out	Remarks
Return-code	N2	O	X	Input -1: no ET.
Cabinet	A8	R	X	The cabinet in which the nickname for which you want to get information is stored. If the nickname is not found in the specified cabinet, but found in cabinet SYSCNT, SYSCNT is returned.
Password	A8	R		The password of the above cabinet.
Nickname	A20	R*	X	The nickname for which you want to get information. Input: either Nickname or ISN; not both.
ISN	P8	R*	X	The ISN of the nickname for which you want to get information. Input: either ISN or Nickname; not both.
Description	A60/1:4		X	The description of the nickname.
Folder-name	A15		X	The folder in which the nickname is stored.
File-name	A15		X	The file within the above folder in which the nickname is stored.
Node-name	A8		X	The name of the external node which has been added by the administrator. Applies only to an external nickname.
Node-parameters	A250		X	The physical address of the external node. Applies only to an external nickname. See <i>External Communication</i> .
Parameter-length	N3		X	Depends upon the Node-parameters. Applies only to an external nickname.
Post-flag	A1		X	Applies only to an external nickname. If marked, a window appears and you can enter additional information before the mail is sent. However, the window only appears when you use the online Con-nect. If you use Z-MAILA to send mail, the window does not appear.

Return Codes

00	Success
02	Invalid cabinet name
03	Password incorrect
04	ISN was not found
08	Supply either ISN or name, not both
09	ISN does not point to correct object
24	Security violation
91	Invalid name
93	The nickname does not exist

Subprograms

Z-120

Z-122

Z-123

Z-147

Z-1200&0