

Console Messages ESY2101W - ESY2109E

Note: All console messages prefixed with ESY2 are valid for BS2000/OSD only.

Message	Explanation	Action
ESY2101W No CONSOLE task started.	Start of CONSOLE task not permitted or internal error occurred during ENTER processing. CONSOLE functionality will not be available for this ESY run.	Check your startup parameters CONACCESS and JOBCONS.
ESY2102W No EVENTING task started.	Start of EVENTING task not permitted or internal error occurred during ENTER processing. EVENTING functionality will not be available for this ESY run.	Check your startup parameters EVENTLEN and JOBEVENT.
ESY2103W Not enough space to create new user entry.	The pool of free user control blocks is exhausted.	Define a larger number for startup parameter NUMUSER and restart Entire System Server.
ESY2104W Central wait point of SERVER has received RC :1:.	The wait request (macro RSOFEI) has returned an unrecoverable error :1:. The SERVER task terminates abnormally.	Please check the return code :1: and contact Software AG if reason of error cannot be solved.
ESY2105E Central wait point of EVENTING task has received RC :1:.	The wait request (macro RSOFEI) has returned an unrecoverable error :1:. The EVENTING task terminates abnormally.	Please check the return code :1: and contact Software AG if reason of error cannot be solved.
ESY2106E No SERVER started.	No server could be started. The Entire System Server terminates abnormally.	Check startup parameters NUMTASK, JOBSERVER and PRMSERVER.
ESY2107E Internal error during :1: of SERVER task.	An internal error has occurred during START or CHECK of a SERVER task. The Entire System Server terminates abnormally if Dynamic Server Management is not running or initialization has not been finished yet.	Please contact Software AG.
ESY2108E Internal error during CHECK of MAIN task.	An internal error has occurred during CHECK of the MAIN task. The SERVER task terminates abnormally due to communication problems with essential parts of the Entire System Server.	Please contact Software AG.
ESY2109E LOAD for module :1: failed - abend.	An error occurred during load (macro BIND) of module :1:. If it is critical, run will terminate. Otherwise, it will continue.	Check your file link settings and the module libraries to correct the problem. Restart Entire System Server.