

Batch Processing of Reports

Most of the reports described in this section are also available in batch. The following table lists the programs and parameters to be used. The reports are printed on Natural printer 1. For OS/390, this means that CMPRT01 must be correctly assigned; for BS2000/OSD this means that the link name P01 must be correctly assigned.

Report ¹	Program	Parameter	Format	Explanation
Log - Terminated Jobs (1) Log - Abended Jobs (2) Log - Jobs not started (3)	REP1--P	FUNCTION-CODE DATE-FROM DATE-TO OWNER (*) NETWORK (*) TIME-FROM TIME-TO COUNT-JOBS (A1)	A = all events in log; B = abended; T = terminated; X = not started 2 2 3 3 N = jobs are not counted. Empty or any entry other than N signifies that jobs are counted.	
Notes about reports 1, 2 and 3:				
<ol style="list-style-type: none"> When these reports are run in batch, a line is written at the bottom of the list containing the total number of jobs in the respective category. This allows you to use reports written to a sequential file as a basis for job statistics programs. In addition, the log user ID and the log execution node are provided for each log message. An entry in the column for the execution node appears only for job accounting records. 				
Network Description (short) (5); (long) (6)	REP40--P	FUNCTION-CODE OWNER (*) NETWORK (*)	(D=detailed, S=short)	
Note about reports 5 and 6:				
REP40--P requires only the parameter FUNCTION-CODE. The parameter NETWORK can be omitted - this means the same as * (all networks). If the parameters OWNER and NETWORK are omitted, this means the same as * * (all owners, all networks).				
Network Job Flow Display (7)	FLOW1--P	OWNER (*) NETWORK (*)		
Schedule of Jobs (8)	REP50--P	DATE-FROM DATE-TO OWNER (*) NETWORK (*)	2 2	
Network Activation Summary (9)	RNWAS--P	OWNER (*) NETWORK (*) DATE	2	
Network Schedule Overview (10)	RNWSC--P	MODE OWNER (*) NETWORK (*) DATE-FROM DATE-TO	A = with schedule, B = to activate, sorted by network, C = to activate, sorted by time 2 2	

JCL Cross Reference, by Files and Members	XRJCL--P	FILE (*) MEMBER (*) LOCATION	If the file has no members, please use - here. A valid JCL location. If this parameter is blank, all locations are valid.	
List of JCL Locations, by Owner, Network	RJCLOC-P	OWNER (*) NETWORK (*)		
Accounting Report	R-JSR--P	FUNCTION (A1) OWNER (*) NETWORK (*) RUN JOB (*) TIME-FROM TIME-TO	A = Accounting Day (YYYYMMDD) or timestamp (YYYYMMDDHHIISS) Day (YYYYMMDD) or timestamp (YYYYMMDDHHIISS)	

* Use an asterisk * as wildcard to enter selection criteria for the parameters.

¹ The menu option numbers in parentheses () apply only if the user's profile allows use of all reports. Otherwise, the numbers will vary.

² Date format is always: YYYYMMDD.

³ Time format is: HH:II:SS. Time specifications "from" or "until" a certain time are optional. If nothing is specified the system uses 00:00:00 and 23:59:59.