

# Console Messages ESY2110E - ESY2119E

---

**Note:** All console messages prefixed with ESY2 are valid for BS2000/OSD only.

Message	Explanation	Action
<b>ESY2110E</b> CONSOLE task has abended with message :1:.	The ENTER processing to start the CONSOLE task has failed with error :1:. The location specified in JOBCONS, the job control, or the ENTER attributes ( parameter PRMCONS ) could be wrong. CONSOLE functionality will not be available for this ESY run.	Correct the error for the next run of Entire System Server.
<b>ESY2111E</b> ADABAS MP - Macro :1: RC :2:.	Macro :1: has returned error :2:. The ADABAS memory pool is not accessible. The task terminates abnormally.	Please contact Software AG.
<b>ESY2112E</b> SERVER task has abended with message :1:.	The ENTER processing to start the SERVER task has failed with error :1:. The location specified in JOBSERVER, the job control, or the ENTER attributes ( parameter PRMSERVER ) could be wrong. The Entire System Server terminates abnormally if Dynamic Server Management is not running or initialization has not been finished yet.	Correct the error and restart Entire System Server.
<b>ESY2113E</b> EVENTING task has abended with message :1:.	The ENTER processing to start the EVENTING task has failed with error :1:. The location specified in JOBEVENT, the job control, or the ENTER attributes ( parameter PRMEVENT ) could be wrong. EVENTING functionality will not be available for this ESY run.	Correct the error for the next run of Entire System Server.
<b>ESY2114E</b> NATURAL-SUB-TASK has abended with message :1:.	The ENTER processing to start the NATURAL-SUB-TASK has failed with error :1:. The location specified in JOBNATSUB, the job control, or the ENTER attributes ( parameter PRMNATSUB ) could be wrong. Natural subtask functionality will not be available for this ESY run.	Correct the error for the next run of Entire System Server.
<b>ESY2115E</b> NATURAL-SUB-TASK initialization failed.	An internal error has occurred during start of Natural subtasking. Natural subtask functionality will not be available for this ESY run.	Please contact Software AG.
<b>ESY2116E</b> Macro :1: RC :2:.	Macro :1: has returned error :2:. The task terminates abnormally.	Please check the return code :2: and contact Software AG if reason of error cannot be solved.
<b>ESY2117E</b> MAIN MP - Macro :1: RC :2:.	This error may occur during initialization of Entire System Server. All tasks started from MAIN have to enable the common ESY MAIN memory pool. Macro :1: has returned error :2:. The task terminates abnormally.	Check if all ESY tasks run in the same user account. If not, change the startup parameters. If there is a different problem, please contact Software AG.
<b>ESY2118E</b> Interrupt Handler - Macro :1: RC :2:.	Macro :1: has returned error :2:. The interrupt handler of the task cannot work properly. The task terminates abnormally.	Please check the return code :2: and contact Software AG if reason of error cannot be solved.
<b>ESY2119E</b> EVENTING MP - Macro :1: RC :2:.	Macro :1: has returned error :2:. The EVENTING memory pool is not accessible. The EVENTING task terminates abnormally.	Please check the return code :2: and contact Software AG if reason of error cannot be solved.

