

DSCHECK: Check Data Storage

```
ADADCK DSCHECK [FILE = { file [FROMRABN = DS-blknum ] [TORABN = DS-blknum ] | file - file } ]  
                [NOOPEN]  
                [NOUSERABEND]  
                [REPAIR]  
                [USAGE]
```

This chapter covers the following topics:

- Optional Parameters and Subparameters
 - Examples
-

Optional Parameters and Subparameters

FILE: Files to Be Checked

The file (or a single range of files) to be checked. If omitted, all files in the database are checked.

FROMRABN: Data Storage Block Number

The RABN of the Data Storage block where the check is to start. This parameter is applicable only if a single file is to be checked.

If omitted, the check starts at the beginning of the first allocated Data Storage extent for the file.

NOOPEN: Prevent Open Synchronization

When starting, ADADCK normally performs a utility open call to the nucleus to assure that no blocks of the affected file or files are still in the nucleus buffer pool. However, this also locks the file for other users. Specifying NOOPEN prevents ADADCK from issuing the open call and blocking file usage for other users.

NOUSERABEND: Termination without ABEND

When an error is encountered while the function is running, the utility prints an error message and terminates with user ABEND 34 (with a dump) or user ABEND 35 (without a dump).

If NOUSERABEND is specified, the utility will *not* ABEND after printing the error message. Instead, the message "utility TERMINATED DUE TO ERROR CONDITION" is displayed and the utility terminates with condition code 20.

REPAIR: Repair the Data Storage Space Table

If ADADCK finds any invalid Data Storage space table elements, it automatically repairs the table if this parameter is supplied.

TORABN: Ending Data Storage Block Number

The RABN of the Data Storage block where the check is to end. This parameter is applicable only if a single file is to be checked.

USAGE: Print Data Storage Block Usage

If USAGE is specified, ADADCK prints a bar graph that shows the number of bytes used in each Data Storage block, the block size, and the percentage of blocks used.

Examples

Check Data Storage and its space table for file 20, print a bar graph of the Data Storage block utilization and repair the space table if required.

```
ADADCK DSCHECK FILE=20, USAGE, REPAIR
```

Check Data Storage and its space table for the files 8 through 12.

```
ADADCK DSCHECK FILE=8-12
```

Check Data Storage and its space table for file 12 in the RABN range 878 through 912.

```
ADADCK DSCHECK FILE=12,  
FROMRABN=878, TORABN=912
```