

# RELO - Storage Thread Relocation

This Natural profile parameter is for mainframes only.

It controls the relocation of the Natural thread after a terminal I/O in a thread environment (CICS, Com-plete, IMS/TM, UTM and Natural as a Server under OS/390).

<b>Possible settings</b>	ON	The Natural thread and all the buffers contained therein can be relocated to another storage area if the original storage area has been occupied by another user after a terminal I/O.
	OFF	<p>No relocation is performed. The Natural thread and all the buffers therein remain located at the same virtual address after the terminal I/O.</p> <p>This setting applies to CICS and Com-plete only. In all other thread environments, Natural cannot guarantee that the thread remains located at the same address.</p> <p><b>Notes for CICS:</b></p> <ul style="list-style-type: none"> <li>• When using TYPE=GETM threads under CICS, RELO=OFF has the same effect as the PSEUDO=OFF setting of the PSEUDO profile parameter. See also TYPE (thread type for group) in the section Natural under CICS in the TP Monitor Interfaces documentation.</li> <li>• A specification of RELO=OFF is ignored for Natural server sessions under CICS using TYPE=GETM threads.</li> </ul>
	FORCE	<p>This will force a relocation of the Natural thread and all the buffers contained therein to another storage area. This can be useful for testing purposes in some environments.</p> <p>This setting applies to CICS, Com-plete and IMS/TM only.</p>
<b>Default setting</b>	ON	
<b>Dynamic specification</b>	YES	
<b>Specification within session</b>	NO	