




PREDICT

Installation
Version 4.2.2 for Mainframes

 **SOFTWARE AG**



This document applies to Predict Version 4.2.2 and to all subsequent releases. Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

© October 2002, Software AG
All rights reserved

Software AG and/or all Software AG products are either trademarks or registered trademarks of Software AG. Other products and company names mentioned herein may be the trademarks of their respective owners.

Table of Contents

Predict Installation on Mainframes	1
Predict Installation on Mainframes	1
Installation Prerequisites	2
Installation Prerequisites	2
General Information	2
Product Requirements	2
Other Related Software AG Products	3
Other Related Products	4
Entire Net-Work	5
Special Considerations For Predict Application Control	5
Accessing the Dictionary Server with Natural for Windows	6
Using Predict in Heterogeneous Environments	7
Installation Jobs/Procedures	7
BS2000/OSD, OS/390, VSE/ESA	7
VM/CMS	8
Using System Maintenance Aid	8
Installation Tape	8
Datasets Required for Predict	8
Copying the Tape Contents to Disk	9
Copying to a BS2000/OSD Disk	9
Copying to a VM/CMS Disk	10
Copying to an OS/390 Disk	11
Copying to a VSE/ESA Disk	12
Which Installation Method?	12
First-Time Installation	12
Upgrading to a new Version of Predict with Inplace Conversion	13
Upgrading from Version 3.4 of Predict	13
Considerations Prior to Upgrading to Version 4.2	13
First-Time Installation	15
First-Time Installation	15
Installing under VM/CMS	15
Installing under BS2000, OS/390 or VSE/ESA with SMA	15
Installation Steps for All Operating Systems	15
Inplace Conversion from a Previous Version	19
Inplace Conversion from a Previous Version	19
Installing under VM/CMS	19
Installing under BS2000, OS/390 or VSE/ESA with SMA	19
Inplace Conversion from Version 4.1	20
Installation Steps	20
Applying Service Packs or Subsequent System Maintenance Levels	25
Applying Service Packs or Subsequent System Maintenance Levels	25
▶ Step 1: Save the user exit routines, other programs delivered in source form, and help texts if you modified them.	25
▶ Step 2: Delete modules no longer used.	25
▶ Step 3: Load Predict System Programs.	25
▶ Step 4: Load Predict XREF System Programs.	25
▶ Step 5: Restore the objects you saved in Step 1 of this description.	25

Predict Installation on Mainframes

-  General Information Provides an overview of the product requirements and the basic installation steps.
-  First-Time Installation Describes the steps involved when you install Predict for the first time.
-  Inplace Conversion from a Previous Version Describes the steps involved when you migrate from an older Predict version using inplace conversion.
-  Applying Service Packs or Subsequent System Maintenance Levels Describes the steps involved when you upgrade an existing Predict environment.

Installation Prerequisites

This document describes step-by-step how to install Predict under the following operating systems:

- BS2000/OSD
- VM/CMS
- OS/390
- VSE/ESA

The steps to be taken depend on which installation method you choose: first-time installation or in-place conversion.

This document covers the following topics:

- General Information
 - Using Predict in Heterogeneous Environments
 - Installation Jobs/Procedures
 - Using System Maintenance Aid
 - Installation Tape
 - Copying the Tape Contents to Disk
 - Which Installation Method?
-

General Information

This information applies to both installation methods - first time installation and in-place conversion. It covers the following topics:

- Product Requirements
- Other Related Software AG Products
- Other Related Products
- Entire Net-Work
- Special Considerations For Predict Application Control
- Accessing the Dictionary Server with Natural for Windows

Product Requirements

The products listed below must be installed in order to use Predict 4.2.

Product Name (Product ID)	Requirements
Natural (NAT)	<p>Natural 3.1.4 or above. If you are using Natural for DB2, Natural for DB2 Version 3.1.5 is required.</p> <p>The following parameter settings are recommended during the installation of Predict 4.2:</p> <ul style="list-style-type: none"> ● MADIO=0 ● MAXCL=0 ● MT=0 ● RI=OFF. <p>The Natural editor must be installed. The Software AG Editor is required for this version of Predict. You are recommended to set the size of the editor buffer pool to 1024k.</p> <p>If you are using SMA, the necessary modules are linked when the SMA parameter SAG-EDITOR is set. If you are installing without SMA, see the Natural Installation Guide for Mainframes.</p>
Adabas (ADA)	<p>Adabas 6.2.1 or higher</p> <p>The following Adabas parameter should be set during the installation of Predict 4.2:</p> <ul style="list-style-type: none"> ● NISNHQ = 200 or greater <p>AOSASM must be linked to the Batch Natural nucleus if AOS is installed.</p> <p>If you are using Adabas Version 7.1 you are recommended to load the Predict system file and the Coordinator FDIC file with index compression.</p>

Other Related Software AG Products

These products are not necessary in order to use Predict 4.2, but if they are installed, the following prerequisites must be met.

Product Name (Product ID)	Requirements
Adabas Online Services (AOS)	Adabas Online Services Version 6.2.1 or above.
Adabas Native SQL (SQL)	Adabas Native SQL Version 2.1 or above.
Adabas SQL Server (ESQ)	Adabas SQL Server Version 1.4.2 or above On mainframes, Interactive Facilities of Adabas SQL Server must be installed within Natural.
Entire System Server (NPR)	(formerly NATURAL PROCESS) Entire System Server Version 2.1.4 or above.
Natural Security (NSC)	The Natural Security version that corresponds to your Natural version.
Natural ISPF (ISP)	Natural ISPF Version 2.4.2 or above.
Natural for Windows (NGU)	Natural for Windows 5.1.1 or above.
Predict Application Control (PAC)	Predict Application Control 2.3.n.
Predict Case (PCA)	Predict Case Version 2.5.2 or above.
Con-form (CMF)	Con-form Version 3.2.3 or above.
Con-nect (CNT)	Con-nect Version 3.2.3 or above. If Con-nect is installed at your site, copy the following modules from SYSCNT2 to SYSDIC to enable the transfer of texts to and from Con-nect: Z-ADD11A, Z-DIS11, Z-ERA11, Z-GET11B, Z-GET11C. See Application Programming Interface in the Con-nect Administration documentation for additional modules that must be copied.
Predict SYSHELP	If SYSHELP is used, you must copy the SYSH* routines from library SYSDICH to a steplib of your application because some routines have changed.
Super Natural (NSN)	Super Natural Version 3.2.1 or above.
Natural Construct (CST)	Natural Construct Version 4.3.1 or above.

Other Related Products

Product Name	Requirements
Natural DB2 Interface	If DB2 is installed, Version 6, Release 1 or above must be installed. Natural DB2 Interface 3.1.5 or above is required.
Natural SQL/DS Interface	If SQL/DS is installed, Version 2, Release 2 or above must be installed.
MS Word	Microsoft Word 6, 7 or 97.

Entire Net-Work

- Entire Net-Work 5.6.1 with ZAP WX53052 or above for mainframes
- Entire Net-Work 2.1.1 or above for UNIX
- Entire Net-Work 2.6.1 or above for workstations
- Entire Net-Work 3.2.3 or above for OpenVMS

These products are required if you are using Predict in a heterogeneous environment.

When the Predict FDIC file is shared between Natural on mainframe and Natural on a Windows, UNIX or OpenVMS platform, Entire Net-Work must be used. For details concerning each platform, see the corresponding **Installation documentation**.

Special Considerations For Predict Application Control

- PAC 2.3.1 and above.

Prerequisites

- The PCF (Predict Control File) must be converted to Predict Version 4.2 format. See the section Conversion in the **Predict Administration documentation**.
- A Coordinator FDIC file must be allocated to the PCF. The Coordinator FDIC of the PCF can be the same as the Coordinator FDIC of the Predict file, but does not have to be.

If the Coordinator FDIC files are identical

If the Coordinator FDIC of the PCF is the same as the Coordinator FDIC of the Predict file, perform the following steps:

1. Start a Natural session and specify FDIC=(dbnr,fnr) of PCF.
2. Call the function Defaults > Coordinator Defaults to specify a Coordinator FDIC for the PCF. See the section Defaults in the **Predict Administration Documentation**.

There is a new function with Predict Application Control Version 2.3 which performs the same. See also the section **Define Coordinator file for PCF** in the **PAC/PAA Release Notes Version 2.3.1**

If the Coordinator FDIC files are different

If the Coordinator FDIC of the PCF is not the same as the Coordinator FDIC of the Predict file, perform the following steps:

1. Load the Coordinator FDIC contained in dataset PRD42n.SYSF using the ADALOD utility (Job I050, Step 0601).
 2. Start a Natural session and specify FDIC=(dbnr,fnr) of PCF.
 3. Call the function Defaults > Coordinator Defaults to specify a Coordinator FDIC for the PCF. See the section Defaults in the **Predict Administration Documentation**.
- The following parameter values must be set when migrating Predict objects from the Development FDIC into PAC. This is applicable to Predict migrations only.

Step 2: Unload PRD from Development
SSIZE=100

Step 3: Load to Control File
DATSIZE=85

Functional Scope

- You can migrate data from Predict 4.2 to PAC 2.3.
- From PAC 2.3, you can migrate data to Predict 4.1 or 4.2.

Note:

If you are migrating from PAC 2.3 to Predict 4.1, please ensure that the system files reference the Predict 4.1 environment in the PRDLOAD step (2nd step in the OS_Predict_MIGRATE_OUT JCL.) This includes not only the FDIC file where the Predict 4.1 data resides, but also the FNAT where the Predict 4.1 software is installed. It may also be necessary to override other system files, such as the FUSER and FSEC.

- With PAC 2.3, you can version Predict 4.1 or 4.2 data.
- You cannot migrate the new object type Trigger in Version 4.2 from a Predict 4.1 environment, even if PAC is using a 4.2 FDIC. See also the section **Symbiosis with Predict** in the **PAC/PAA Release Notes Version 2.3.1**.

Accessing the Dictionary Server with Natural for Windows

With dictionary servers, you can access remote DDMs, free rules and automatic rules maintained in Predict once you have access to Predict on a mainframe or UNIX host. Predict rules can only be used by accessing Predict on a UNIX or mainframe server.

Additional Prerequisites

The following products must be installed in addition to the products listed above under Product Requirements:

<p>Client Side</p> <ul style="list-style-type: none"> ● Natural for Windows 4.1.2 or above ● Entire Net-Work 2.6.1 for workstations or above
<p>Server Side</p> <ul style="list-style-type: none"> ● Entire Net-Work 5.6.1 with ZAP WX53052 or above for mainframes ● Entire Net-Work 2.1.1 or above for UNIX ● Entire Net-Work 2.6.1 or above for workstations ● Entire Net-Work 3.2.3 or above for OpenVMS ● Entire Broker 2.1.1 or above

Starting the Server

Please read the **Natural RPC documentation** before starting the RPC server. The dictionary server name must be known in order to set up the remote dictionary access on the client side.

Accessing the Server

To access the server, you need a Net-Work connection to the server’s Net-Work. Please ask your data center for the appropriate settings.

Before starting Natural, define the dictionary server using the Natural for Windows NATPARM utility with the following two steps:

1. Define a logical dictionary server. For this you need to know
 - the server name of the dictionary server (DDM server) that has been defined to the Entire Broker on the server system.
 - the node name on which this server is running. This is the name of the broker.

Ask your data center for these names.

The logical dictionary server is defined in the menu Global CONFIG File > Dictionary Server Assignments.

2. Set the parameter USEDIC (remote dictionary access) to a logical dictionary server name that has been defined in the global CONFIG file.

When running Natural using this parameter module, you must have access to the server. To check whether you are connected to the server, use the command MENU from SYSRPC to ping the server. You therefore need to define the server using the SERVER MAINTENANCE option.

Please ensure that the Server Node Classification has been set to the appropriate values. You can then use the SERVER COMMAND EXECUTION option to ping the server. The server should reply "I'm still up!".

Note:

It is not necessary to generate a client stub to access the server.

Using Predict in Heterogeneous Environments

The following applies:

- If you are using Natural on the mainframe, the Predict system file FDIC must be located in the mainframe database.
- If you want to access FDIC only under Natural for Windows, UNIX or OpenVMS platforms, FDIC can be located in an Adabas database on any of these platforms.
- If you share the FDIC file between Natural on the mainframe and a Natural for Windows or UNIX installation, your FDIC file must be located on the mainframe and you need to configure the translation definitions in Entire Net-Work. Add the following translation definitions to your Entire Net-Work on the mainframe:

```
Translate Define ADD ID=(<FDIC-DBnr>,<FDIC-Fnr>) Field=LO, FORMAT=(A,33,X,2)
Translate Define ADD ID=(<FDIC-DBnr>,<FDIC-Fnr>) Field=LK, FORMAT=(X,2,A,88)
Translate Define ADD ID=(<FDIC-DBnr>,<FDIC-Fnr>) Field=LJ, FORMAT=(A,16,X,2)
Translate Define ADD ID=(<FDIC-DBnr>,<FDIC-Fnr>) Field=L2, FORMAT=(X,2,A,32)
```

- For the Predict Coordinator FDIC file, the same translation definition as described above must be configured, but using the following syntax. Replace the ID parameter in the four above definitions with:

```
ID=( <Coordinator-DBnr> , <Coordinator-Fnr> )
```

- If you are using the Predict Coordinator, it must be installed on the same platform as the main FDIC.
- Set the Coordinator defaults parameter Clear with System Utility to N.

Installation Jobs/Procedures

The method used for installing Predict depends on your operating system environment.

BS2000/OSD, OS/390, VSE/ESA

For these operating systems, the installation of Software AG products is performed by installation jobs. These jobs are either adapted manually or generated by System Maintenance Aid (SMA), see Using System Maintenance Aid.

For each step of the installation procedure described below, the job number of a job performing the respective task is indicated. This job number refers to an installation job generated by SMA. If you are not using SMA, a sample installation job of the same number is provided in the job library on the Predict installation tape; you must adapt this example job to your requirements. Please note that the job numbers on the tape are preceded by a

product code (for example, PRDI061).

VM/CMS

The installation of Software AG products is performed by installation procedures. Sample procedures are provided on the installation tape.

Note:

These procedures are only examples and must be adapted to your environment as required.

Using System Maintenance Aid

Note:

System Maintenance Aid (SMA) is not available for the operating system VM/CMS.

If you are using Software AG's System Maintenance Aid (SMA) for the installation process, perform the following before generating jobs:

1. Load the SMA table data as described in the SYSTEM MAINTENANCE AID documentation (if you have not already done so).
2. Set PRD42n in the list of available products for your environment to 'TO BE INSTALLED'.

Then perform one of the following steps depending on the installation method you choose:

- If you are performing a First-Time Installation, adapt parameters FDIC Fnr and FDIC-DBID in the parameter group FILNUM to the required values. Then make the appropriate settings in parameter group OPTION as shown in table below.
- If you are performing an Inplace Conversion (Predict Version 4.1 is marked as 'INSTALLED' in your SMA environment), you can convert the installed version to Version 4.2 with the following settings in parameter group OPTION:

SMA Switch	For First-Time Installation	For Migrate from Version 4.1
PRD-FIRST-INSTALL	Y	N
PRD-MIGR-FR41	N	Y

Note:

Leaving a field blank is the equivalent of entering N.

See the **System Maintenance Aid documentation** for more information.

Installation Tape

The installation tape contains the datasets listed in the table below. The sequence of the datasets is shown in the Report of Tape Creation which accompanies the installation tape. The notation *n* in dataset names represents the SM level of the product, for example 1 in Predict Version 4.2.1.

Datasets Required for Predict

The following datasets are required to install Predict. The datasets delivered (X) depend on the operating system on which you are installing.

Dataset Name	BS2000/ OSD	VM/CMS	OS/390	VSE/ESA	Contents
PRD42n.JOBS	X		X		Sample installation jobs.
PRD42n.Tape		X			Sample installation jobs.
PRD42n.INPL	X	X	X	X	Natural modules of Predict in INPL format. This dataset also contains Predict error messages.
PXR11n.INPL	X	X	X	X	Natural module of Predicts LIST XREF in INPL format. This dataset also contains Predict error messages.
PRD42n.SYSF	X	X	X	X	Predict system file in Adabas 6 ADAULD format without database description.
PRD42n.DATA	X	X	X	X	Predict description of Predict 4.2 in Migrate 4.2 format.
PRD42n.DEMO	X	X	X	X	Predict Demo DB in Migrate 4.2 format. This includes sample files such as EMPLOYEES and VEHICLES and other sample data.
PRD42n.LIBJ				X	Sample installation jobs.
PRD42n.DE41	X	X	X	X	List of modules no longer used by Predict since version 4.1.
PRD42n.DE42	X	X	X	X	List of modules no longer used by Predict.
CST431.CP42	X	X	X	X	Interface for Natural Construct version 4.3.1. To load this dataset, use the INPL utility.

Copying the Tape Contents to Disk

The steps required to copy the contents of the installation tape to disk depend on your operating system environment.

- BS2000/OSD
- VM/CMS
- OS/390
- VSE/ESA

Copying to a BS2000/OSD Disk

If you are not using SMA, copy datasets from tape to disk using the steps below. The following values must be supplied:

- In the dataset names, replace nnn with the current version number of the datasets.
- Replace all xxxxxx with the volume serial number of the tape.

Step 1 - Copy Dataset PRD42n.JOBS to Disk

Copy the job dataset PRD42n.JOBS from tape to disk using the BS2000/OSD utility PERCON or EDT.

If using PERCON, issue the following commands:

```

/FILE PRD42n.JOBS,VOL=xxxxxx,DEV=T9G -
/ ,STATE=FOREIGN,FSEQ=UNK,LINK=PCIN
/FILE P.PRD42n,LINK=PCOUT
/EXEC PERCON
END

```

If using EDT, issue the following commands:

```

/FILE PRD42n.JOBS,VOL=xxxxxx,DEV=T9G -
/ ,STATE=FOREIGN,FSEQ=UNK,LINK=EDTSAM
/EXEC EDT
@ READ '/'
@ SY '/REL EDTSAM'
@ WRITE 'P.PRD42n'
@ HALT

```

Step 2 - Call Predict

Then issue the following command:

```

/CALL PRD42n , PRODUCT=PRD42n

```

A sample job library "LIB.PRD42n" will be created from the procedure dataset.

Copying to a VM/CMS Disk

To position the tape for the TAPE LOAD command, calculate the number of tape marks as follows:

If the sequence number of PRD42n.TAPE - as shown by the Report of Tape Creation - is n , you must position over $3n-2$ tape marks (that is, FSF 1 for the first dataset, FSF 4 for the second, etc.).

Access the disk that is to contain the Predict installation files as minidisk.

Ask the system operator to attach a tape drive to your virtual machine at the address X'181' and mount the Predict installation tape.

When the tape has been attached, enter the VM/CMS command

```

TAPE REW

```

Position the tape by entering the VM/CMS command

```

TAPE FSF n

```

where n is calculated as above ($3n-2$).

Load the Predict/VM/CMS installation material with the VM/CMS command

```

TAPE LOAD * * <minidisk>

```

You may wish to keep the tape drive attached to your virtual machine, because the tape is still needed in the installation procedure.

Copying to an OS/390 Disk

If you are using System Maintenance Aid (SMA), refer to the **SMA documentation** (included on the current edition of the Natural documentation CD).

If you are **not** using SMA, follow the instructions below.

This section explains how to:

- Copy data set COPY.JOB from tape to disk.
- Modify this data set to conform with your local naming conventions.

The JCL in this data set is then used to copy all data sets from tape to disk.

If the datasets for more than one product are delivered on the tape, the dataset COPY.JOB contains the JCL to unload the datasets for all delivered products from the tape to your disk.

After that, you will have to perform the individual install procedure for each component.

Step 1 - Copy data set COPY.JOB from tape to disk

The data set COPY.JOB (label 2) contains the JCL to unload all other existing data sets from tape to disk. To unload COPY.JOB, use the following sample JCL:

```
//SAGTAPE JOB SAG,CLASS=1,MSGCLASS=X
//* -----
//COPY EXEC PGM=IEBGENER
//SYSUT1 DD DSN=COPY.JOB,
// DISP=(OLD,PASS),
// UNIT=(CASS,,DEFER),
// VOL=(,RETAIN,SER=<Tnnnnn>),
// LABEL=(2,SL)
//SYSUT2 DD DSN=<hilev>.COPY.JOB,
// DISP=(NEW,CATLG,DELETE),
// UNIT=3390,VOL=SER=<vvvvvv>,
// SPACE=(TRK,(1,1),RLSE),
// DCB=*.SYSUT1
//SYSPRINT DD SYSOUT=*
//SYSIN DD DUMMY
//
```

Where:

- <hilev> is a valid high level qualifier
- <Tnnnnn> is the tape number
- <vvvvvv> is the desired volser

Step 2 - Modify COPY.JOB to conform with your local naming conventions

There are three parameters you have to set before you can submit this job:

- Set HILEV to a valid high level qualifier.
- Set LOCATION to a storage location.
- Set EXPDT to a valid expiration date.

Step 3 - Submit COPY.JOB

Submit COPY.JOB to unload all other data sets from the tape to your disk.

Copying to a VSE/ESA Disk

If you are not using SMA, copy the sublibrary containing the sample installation jobs from tape using the sample JCS below. The following values must be supplied in the JCS:

- The notation XXXXXX represents the tape volume serial number as shown in the Report of Tape Creation.
- The notation cuu represents the physical unit address of the tape drive.
- The notation xx represents the file sequence number as shown in the Report of Tape Creation. If your library is the first dataset on the tape, leave out the "// MTC..." instructions.
- The notation n represents the SM number of the product.
- Now use job TAPE from this job library to restore the Predict sublibrary from tape.

All further datasets will be used directly from tape by the installation jobs.

```
* $$ JOB JNM=PRDJOB,CLASS=0,DISP=D,LDEST=*,SYSID=1
* $$ LST CLASS=A,DISP=D
// JOB PRDJOB
// ASSGN SYS005,IGN
// ASSGN SYS006,cuu,VOL=XXXXXX
// MTC REW,cuu
// MTC FSF,SYS006,xx
* *** Now processing PRD42n.LIBJ - Sublibrary PRD42nJ ***
// EXEC LIBR,PARM='MSHP'
RESTORE SUBLIB=SAGLIB.PRD42nJ:SAGLIB.PRD42nJ
TAPE=SYS006 -
LIST=YES -
REPLACE=NO
/*
// MTC REW,SYS006
/*
/&
* $$ EOJ
```

The sample jobs directly use the sequential datasets from tape.

The dataset type and the space each dataset requires on disk are shown in the Report of Tape Creation.

Which Installation Method?

The installation method you choose depends on whether Predict is already installed at your site. There are two methods available: first-time installation and inplace conversion.

First-Time Installation

If you are installing Predict for the first time or in an environment where Predict is not yet installed, go straight to the section First-Time Installation.

Upgrading to a new Version of Predict with Inplace Conversion

When upgrading from Version 4.1 of Predict, data in the format of the previous version must be converted to Predict 4.2 format.

The Predict data is converted directly on your Predict system file to Predict 4.2 format.

See the section Inplace Conversion for the steps required.

Upgrading from Version 3.4 of Predict

Note:

If the last Predict version installed in your environment was Version 3.4 or below, delete all modules no longer used by Predict since Version 4.1 with dataset PRD42n.DE41 using the Natural utility INPL (Job I051, Step 0614).

Then perform a first-time installation and then transfer the data using Predict Coordinator.

It is strongly recommended to unload the data in the source environment using Internal-ID=Y.

Considerations Prior to Upgrading to Version 4.2

Superfluous Fields

A Predict system file converted with Inplace conversion will still contain a number of Adabas fields no longer used in Predict 4.2. These can be ignored.

User Exit Routines

Predict provides a number of user exits which can be used to customize many Predict functions to meet special needs. Sample user exit routines illustrating the use of user exits and explaining the parameters are delivered with Predict.

All user exit routines from previous Predict versions with the prefix U- together with their parameter data areas will be replaced by new sample routines during the installation.

Other Programs Delivered in Source Form

In addition to user exits, a number of other Predict programs are delivered in source form. During installation, these source programs replace those delivered with the previous Predict version.

The following source programs in the library SYSDIC are replaced:

EXIT	MAIN	MAINM1	PUNCH01
------	------	--------	---------

The following type-dependent user exits are also replaced:

ACM**EX	CAT**EX	PUR**EX
---------	---------	---------

Note:

The asterisks above represent an object type code, for example FI or SY.

If you adapted any of these programs to meet special needs at your site, save them to a different library before starting the installation.

User Programs which access the Predict System File

All fields in the Predict system file (FDIC) that have been modified since the last version are assigned the keyword SAG-PRD-V42-MOD.

All new fields in Predict 4.2 are assigned the keyword SAG-PRD-V42.

All fields that are no longer used in Predict 4.2 are assigned the keyword SAG-PRD-V42-DEL.

If you have written your own programs which access these fields in the Predict system file, check that these programs are still compatible with these modified fields.

To access Predict data, use the user exit USR1051N.

Help Texts

Predict supplies a large number of online help texts as Natural text members with the prefix H- in the library SYSDIC. These texts can be customized and extended with the special function Maintain Predict Help Texts.

All help texts with the prefix H- are replaced during installation. To prevent user-modified help texts being replaced with new SAG-supplied texts, rename the prefix H- of modified help texts to T-.

If a help text with the prefix T- exists, this is always used by the Predict help system instead of the standard help text with the prefix H-.

First-Time Installation

This section covers the following topics:

- Installing under VM/CMS
 - Installing under BS2000, OS/390 or VSE/ESA with SMA
 - Installation Steps for All Operating Systems
-

Installing under VM/CMS

- Read the file INSTALL.README.
- Copy the tape contents to disk as described in the section General Information for VM/CMS
- Perform the Installation Steps described below for all operating systems.

Installing under BS2000, OS/390 or VSE/ESA with SMA

1. Set the SMA switches as shown in the table below.

SMA Switch	
PRD-FIRST-INSTALL	Y
PRD-MIGR-FR41	N

Note:

Leaving a field blank is the equivalent of entering N.

2. Copy the tape contents to disk.
The steps required depend on your operating system environment and are described in the section **Copying the Tape Contents to Disk** for
 - BS2000/OSD
 - OS/390
 - VSE/ESA
3. Perform the following installation steps.

Installation Steps for All Operating Systems

Note:

If the last Predict version installed in your environment was Version 3.4 or below, delete all modules no longer used by Predict since Version 4.1 with dataset PRD42n.DE41 using the Natural utility INPL (Job I051, Step 0614).

Step 1 - Load Predict System File

(Job I050, Step 0600)

Load the Predict 4.2 system file contained in dataset PRD42n.SYSF using the Adabas utility ADALOD.

Use ADALOD parameter VERSION=6.

▶ Step 2 - Load Coordinator FDIC

(Job I050, Step 0601)

Load the Coordinator FDIC contained in dataset PRD42n.SYSF using the Adabas utility ADALOD.

Use ADALOD parameter VERSION=6.

▶ Step 3 - Load Predict System Programs

(Job I061, Step 0600)

The Predict system programs are contained in the dataset PRD42n.INPL and are loaded to your Natural system file (FNAT) using the Natural utility INPL. This dataset also contains the Predict error messages.

▶ Step 4 - Load Predict XREF System Programs

(Job I061, Step 0601)

The Predict XREF system programs are contained in the dataset PXR11n.INPL and are loaded to your Natural system file (FNAT) using the Natural utility INPL. This dataset also contains the Predict XRef error messages.

▶ Step 5 - Define the Predict Libraries to Natural Security manually

If Natural Security is installed, define the following libraries to Natural Security:

SYSDIC, SYSDICBE, SYSDICCO, SYSDICH, SYSDICMA

This step must be performed manually.

▶ Step 6 - Copy DDMs from Natural system file FNAT to the Predict system file FDIC

(Job I200, Step 0600)

If you were previously using Natural without Predict, the DDMs were stored on the Natural system file. With Predict, the DDMs are stored on the Predict system file.

▶ Step 7 - Relink your Natural Nucleus

(Job I060 for Batch Mode or Job I080 for Online Operation)

Predict requires the following Natural parameter settings:

Note:

The size parameters are recommendations only. It may be necessary to adapt these values to your particular environment.

Note:

Setting BPSFI to ON may cause a NAT0933, because programs with identical names are contained in different libraries starting with the prefix SYSDIC. You are recommended to set BPSFI=OFF.

- DATSIZE must be at least 250.
- SSIZE=64
- RI=OFF
- If you are using work files, you are recommended to specify WORK=(...,OPEN=ACC) instead of using the Natural default
- If Predict XRef data is to be used:
set the XREF parameter to ON or FORCE.

Adapt your Natural parameter module with the new parameters and assemble it.

Link the new Natural parameter module and the following modules to the environment-independent part of the Natural nucleus:

Natural Version	Operating System	Module	Load Library
3.1	BS2000/OSD	PRDXREF	NAT31n.MOD
3.1	VM/CMS	PRDXREF	NAT31n.TAPE
3.1	OS/390	PRDXREF	NAT31n.LOAD
3.1	VSE/ESA	PRDXREF	NAT31n.LIBR

Note:

For Natural Version 3.1.5, use Module PRDXR34.

For details, see the **Natural Installation Guide for Mainframes** and the **Natural Operations for Mainframes documentation**.

▶ Step 8 - Define Coordinator FDIC in new SYSDIC manually

To set up your environment so you can use the Coordinator, start a Predict 4.2 online session (using the newly installed FDIC file) and perform the following:

- Log on to the library SYSDIC
- Call the Function Main Menu by entering MENU at the NEXT prompt
- Call the function Defaults > Coordinator Defaults
- Specify parameters Coordinator FDIC DBnr/Fnr with the file number and database number of the Coordinator FDIC added in Step 2.

▶ Step 9 - Load the Predict Description of the Predict System File

(Job I500, Step 0605)

This step is optional. Please note that, due to the number of checks performed by the Coordinator when loading this dataset, this step may take a long time.

The installation dataset PRD42n.DATA contains a description of the Predict 4.2 system file in Migrate 4.2 format. Load the description into the Predict system file with the Predict Coordinator.

Note:

No support is guaranteed if you manipulate the Predict system file with your own programs.

The following syntax is used:

```
LOGON SYSDICBE
MENU
LOAD OBJECTTYPE ALL,REPLACE=Y,ADA=N
FIN
```

If a previous import operation with the Coordinator terminated abnormally for any reason, the Coordinator FDIC is locked and a corresponding message is given. Enter the following commands to clear the Coordinator FDIC:

```
LOGON SYSDIC
MENU
SPECIAL REFRESH
FIN
```

▶ Step 10 - Load the Predict Example Data

(Job I500, Step 0606)

This step is optional. Please note that, due to the number of checks performed by the Coordinator when loading this dataset, this step may take a long time.

The installation dataset PRD42n.DEMO contains the example data in Migrate 4.2 format. Load the description into the Predict system file with the Predict Coordinator. The following syntax is used:

```
LOGON SYSDICBE
MENU
LOAD OBJECTTYPE ALL,REPLACE=Y,ADA=N
FIN
```

If a previous import operation with the Coordinator terminated abnormally for any reason, the Coordinator FDIC is locked and a corresponding message is returned. Enter the following commands to clear the Coordinator FDIC:

```
LOGON SYSDIC
MENU
SPECIAL REFRESH
FIN
```

▶ Step 11 - Install Natural Construct Interface

If you are working with Natural Construct Version 4.3.n, use the Natural INPL utility to install the interfaces of Natural Construct using dataset CST431.CP42 as input.

Your first-time installation is now complete.

Inplace Conversion from a Previous Version



The inplace conversion will result in considerable modifications to the internal structure of your dictionary data. Software AG recommends that, before you execute the following installation steps you back up your Predict system file using the backup procedures usually performed in your environment.

Please read the following operating system specific information before you start installing Predict.

This section covers the following topics:

- Installing under VM/CMS
 - Installing under BS2000, OS/390 or VSE/ESA with SMA
 - Inplace Conversion from Version 4.1
-

Installing under VM/CMS

- Read the file INSTALL.README.
- Copy the tape contents to disk as described in the section **Copying the Tape Contents to Disk** for VM/CMS
- For the conversion from Version 4.1, perform the Installation Steps described below for all operating systems and continue.

Installing under BS2000, OS/390 or VSE/ESA with SMA

1. Set the SMA switches as shown in the table below.

SMA Switch	For Migrate from Version 4.1
PRD-FIRST-INSTALL	N
PRD-MIGR-FR41	Y

Note:

Leaving a field blank is the equivalent of entering N.

2. Copy the tape contents to disk.
The steps required depend on your operating system environment and are described in the section **Copying the Tape Contents to Disk** for
 - BS2000/OSD
 - OS/390
 - VSE/ESA
3. For the conversion from Version 4.1, perform the following Installation Steps and continue.

Inplace Conversion from Version 4.1

The inplace conversion will result in considerable modifications to the internal structure of your dictionary data. Software AG recommends that, before you execute the following installation steps you back up your Predict system file using the backup procedures usually performed in your environment.

Before starting installation with this method, carefully read the section Conversion in the **Predict Administration documentation**.

Use the function "Conversion defaults" to specify new object-type, association or retrieval-model names/codes for user-defined object types, associations or retrieval models, defined in earlier versions of Predict, if the old names and codes are now reserved. You will not be able to continue the Conversion until valid names/codes have been specified.

Note:

There are no physical changes in the Predict system file from Version 4.1 to Version 4.2.

Installation Steps

Perform the following steps after copying the tape contents to disk.

▶ **Step 1 - Delete Modules No Longer Used**

(Job I051, Step 0615)

Predict modules from earlier versions which were copied to libraries different from the original libraries after installation must be deleted from these libraries using the Natural utility INPL with the dataset PRD42n.DE42 as input.

▶ **Step 2 - Load Predict System Programs**

(Job I061, Step 0600)

The Predict system programs are contained in the dataset PRD42n.INPL. Load these programs into your Natural system file using the Natural utility INPL. This dataset also contains the Predict error messages.

▶ **Step 3 - Load Predict XREF System Programs**

(Job I061, Step 0601)

The Predict XREF system programs are contained in the dataset PXR11n.INPL. Load these programs into your Natural system file (FNAT) using the Natural utility INPL. This dataset also contains the Predict XRef error messages.

▶ **Step 4 - Specify the Conversion Defaults Manually**

Before performing the data conversion, log on to the library SYSDICCO, call the Conversion Utility Menu by entering MENU at the NEXT prompt and select the function "Conversion defaults".

Conversion defaults are used to specify new object-type, association or retrieval-model names/codes for user-defined object types, associations or retrieval models defined in earlier versions of Predict if the old names and codes are now reserved.

The following object-type, association and retrieval-model names/codes are reserved in Predict Version 4.2:

Reserved Object Type	
Names	Codes
TRIGGER	TR
VISTA-DA	
VISTA-FI	

Reserved Retrieval Model	
Model Name	Object Type
AP	SY

Reserved Association		
Object Type	Active Code	Passive Code
(FI->TR)	TR	FI
(PR->FI)	IN	IP
(PR->FI)	RE	RS
(SY->SY)	CS	CS
(SY->PR)	CP	CP
(SY->VE)	CV	CV
(SY->FI)	CF	CF
(SY->SY)	LI	LI
(PR->PR)	MS	MS

Example

In Predict Version 4.1 you defined a UDE with object type name Trigger and Code TI. In Predict Version 4.2, Trigger is the name of a predefined object type and is not permitted as a UDE.

If you call the function Conversion defaults, the following screen appears:

13:41:46	***** P R E D I C T 4.2.2 *****	2002-07-31
	- Conversion Defaults -	
		Added 2002-07-31 at 16:03
		by GER
Object type code	Object type name	Retrieval model
	TRIGGER	

The function lists all UDEs which are in conflict with the new version. Because the code TI is not reserved, this does not appear in the list and does not need to be changed. You do, however, have to change the object type name Trigger before you can convert your data from Version 4.1. Enter under Object type name a new name (which is not reserved) for your UDE and press ENTER.

▶ Step 5 - Convert the Data on the Predict System File to 4.2 Format

(Job I200, Step 0606)

This job converts Predict 4.1 data to Version 4.2 format. If the data on your Predict system file is already in Version 4.2 format, a corresponding message is returned.

```
LOGON SYSDICCO
MENU
CONVERT VERSION42
FIN
```

Now the data is in Version 4.2 format. We recommend you save your Predict system file in Version 4.2 format before proceeding with the steps below.

▶ Step 6 - Relink your Natural Nucleus

(Job I060 for Batch Mode, Job I080 for Online Operation)

Predict requires the following Natural parameter settings:

Note:

The size parameters are only recommendations. It may be necessary to adapt these values to your particular environment.

Note:

Setting BPSFI to ON may cause a NAT0933, because programs with identical names are contained in different libraries starting with the prefix SYSDIC. You are recommended to set BPSFI=OFF.

- DATSIZE must be at least 200.
- SSIZE=64
- RI=OFF
- If you are using work files, you are recommended to specify WORK=(...,OPEN=ACC) instead of using the Natural default.
- If Predict XRef data is to be used:
set the XREF parameter to ON or FORCE.

Adapt your Natural parameter module with the new parameters and assemble it.

Link the new Natural parameter module and the following modules to the environment-independent part of the Natural nucleus:

Natural Version	Operating System	Module	Load Library
3.1	BS2000/OSD	PRDXREF	NAT31n.MOD
3.1	VM/CMS	PRDXREF	NAT31n.TAPE
3.1	OS/390	PRDXREF	NAT31n.LOAD
3.1	VSE/ESA	PRDXREF	NAT31n.LIBR

Note:

For Natural Version 3.1.5, use Module PRDXR34.

For details see the **Natural Installation documentation for Mainframes** and the **Natural Operations documentation for Mainframes**.

▶ Step 7- Add Default Definitions

If you are using Predict Security, you should add default definitions for the new object types using the function Add NSC Default Definitions.

This function is used to add the NSC external object types and default values for these. If an NSC external object type is specified, a window appears in which you can define the access modes for this type. If no NSC external object is specified, a series of windows appears in which you can define the access modes for all four types.

```

17:34:12          ***** P R E D I C T 4.2.2 *****          2002-07-31
Plan    7          - Maintain NSC Definitions -

+-----+ NSC External Object Type
! Default for NSC ext. object type PL !
!                                     ! PO PRD-Docu-Object
! Read      Y (Y,N)                   ! PE PRD-Ext-Object
! Add       Y (Y,N)                   ! PF PRD-Function
! Modify    Y (Y,N)                   ! PL PRD-3Gl-Library
! Delete    Y (Y,N)                   ! ' ' All
+-----+

```

When the access mode values have been specified, a report list is created of default definitions to be added. Confirm this list to add the definitions to Natural Security.

Note:

Only objects contained in the report list will be added. You should page to the end of this list to make sure it is complete.

Note:

This function can be run again at any time, for example after adding new user-defined object types in metadata administration. This function adds default definitions for the new object types.

▶ Step 8 - Load the Predict Description of the Predict System File

(Job I500, Step 0605)

This step is optional. Please note that, due to the number of checks performed by the Coordinator when loading this dataset, this step may take a long time.

The installation dataset PRD42n.DATA contains a description of the Predict 4.2 system file in Migrate 4.2 format. Load the description into the Predict system file with the Predict Coordinator.

Note:

No support is guaranteed if you manipulate the Predict system file with your own programs.

The following syntax is used:

```

LOGON SYSDICBE
MENU
LOAD OBJECTTYPE ALL,REPLACE=Y,ADA=N
FIN

```

If a previous import operation with the Coordinator terminated abnormally for any reason, the Coordinator FDIC is locked and a corresponding message is returned. Enter the following commands to clear the Coordinator FDIC:

```
LOGON SYSDIC
MENU
SPECIAL REFRESH
FIN
```

▶ Step 9 - Load the Predict Example Data

(Job I500, Step 0606)

This step is optional. Please note that, due to the number of checks performed by the Coordinator when loading this dataset, this step may take a long time.

The installation dataset PRD42n.DEMO contains the example data in Migrate 4.2 format. Load the description into the Predict system file with the Predict Coordinator. The following syntax is used:

```
LOGON SYSDICBE
MENU
LOAD OBJECTTYPE ALL,REPLACE=Y,ADA=N
FIN
```

If a previous import operation with the Coordinator terminated abnormally for any reason, the Coordinator FDIC is locked and a corresponding message is returned. Enter the following commands to clear the Coordinator FDIC:

```
LOGON SYSDIC
MENU
SPECIAL REFRESH
FIN
```

▶ Step 10 - Install Natural Construct Interface

If you are working with Natural Construct Version 4.3.n, use the Natural INPL utility to install the interfaces of Natural Construct using dataset CST431.CP42 as input.

Your inplace conversion is now complete

Applying Service Packs or Subsequent System Maintenance Levels

When migrating from Predict Version 4.2.1 to Predict Version 4.2.n ($n > 1$), please observe the information below. If you have already installed Predict Version 4.2.1 in your environment, no conversion of your FDIC file is necessary.

Perform the following steps after copying the tape contents to disk as described in the Predict Installation Documentation.

Note:

If you are working with SYSTEM MAINTENANCE AID, set the following parameters in parameter group OPTION to N before starting the installation:

- PRD-MIGR-FR41
- PRD-FIRST-INSTALL

Perform the following steps:

▶ **Step 1: Save the user exit routines, other programs delivered in source form, and help texts if you modified them.**

▶ **Step 2: Delete modules no longer used.**

See Step 1 (Job I051, Step 0615) in the section **Inplace Conversion**.

▶ **Step 3: Load Predict System Programs.**

See Step 2 (Job I061, Step 0600) in the section **Inplace Conversion**.

▶ **Step 4: Load Predict XREF System Programs.**

See Step 3 (Job I061, Step 0601) in the section **Inplace Conversion**.

▶ **Step 5: Restore the objects you saved in Step 1 of this description.**