

RELO - Storage Thread Relocation

This Natural profile parameter is for mainframes only.

It controls the relocation of the Natural thread after a terminal I/O in a thread environment (CICS, Com-plete, IMS/TM, UTM and Natural Server under OS/390).

| | | |
|-------------------------------------|-------|---|
| Possible settings | ON | The Natural thread and all the buffers contained therein can be relocated to another storage area if the original storage area has been occupied by another user after a terminal I/O. |
| | OFF | No relocation is performed. The Natural thread and all the buffers therein remain located at the same virtual address after the terminal I/O. This setting applies to CICS and Com-plete only. In all other thread environments, Natural cannot guarantee that the thread remains located at the same address. Note for CICS: When using TYPE=GETM threads under CICS, RELO=OFF has the same effect as the PSEUDO=OFF setting of the PSEUDO Parameter. See also TYPE - Thread Type for Group in the section Natural under CICS in the TP Monitor Interfaces documentation. |
| | FORCE | This will force a relocation of the Natural thread and all the buffers contained therein to another storage area. This can be useful for testing purposes in some environments. This setting applies to CICS, Com-plete and IMS/TM only |
| Default setting | ON | |
| Dynamic specification | YES | |
| Specification within session | NO | |