


Navigating Through the Transport Service Administration

This chapter covers the following topics:

- Invoking the Transport Service Administration Menu
 - The Transport Service Administration Menu
 - Transport Service Commands and PF-Key Assignments
-

Invoking the Transport Service Administration Menu

The following diagram shows the path you must take to invoke this screen. Functions which do not solely pertain to the transport service are shown in the light green boxes. For further information, see *External Mail Nodes*.



The Transport Service Administration Menu

All transport service functions such as creating and maintaining queues are accessed via the Transport Service Administration screen. To invoke this screen:

- Select the Maintain Mail Nodes function on the Administration - External Mail Nodes screen and press ENTER to display the Maintain Mail Node window.
- Select the "Transport Service" field and press ENTER. As a result, the screen below is displayed.

```
1:16 PM          * * * C O N - N E C T 3 * * *          14.Feb.94
Cabinet LS      Transport Service Administration        A06740

Select a function:      _ Queue Maintenance
                        _ Routing Entry Maintenance
                        _ Log Information Maintenance
                        _ Initialization
                        _ Address Conversion

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help Menu Quit Queue Route Logs Init AddrC
Mark item(s) from the list above or press a PF-key
```

For a description of the transport service functions and screens which can be obtained from this menu, see *Maintaining the Transport Service*.

You can select a function by marking it with any character and pressing ENTER or by pressing the PF-key assigned to the function.

Transport Service Commands and PF-Key Assignments

Each transport service screen contains a PF-key line. If you press PF2, you are always returned to the Transport Service Administration screen (if you press PF2 on the Transport Service Administration screen, you are returned to the Administration - Main Menu). If you press PF3, you are always returned to the previous screen.

Several of the screens include a cmd-column - the commands which apply to the items listed in that screen are displayed at the bottom of the screen.

The following are commands which can be issued in a transport service screen. They are issued by entering the letters assigned to the command in the cmd-column adjacent to an item and pressing ENTER:

Command	Description
EI	Erase Items - erases the marked item.
MO	Modify - highlighted fields can be modified. Once you have completed entering the information, press PF5 to confirm the modification.
ST	Start queue - starts the marked queue.
SP	Stop queue - stops the marked queue.
RE	Rest queue - resets the marked queue.
DI	Display item - displays the marked item.
DQ	Display queue - displays the marked queue.
EQ	Erase queue - erases the marked queue.