

Download Address Maintenance

This chapter covers the following topics:

- Download Address Maintenance Screen
- Return to Top of List
- Display Additional Address Information
- Erase an Address
- Import an Address
- Find Addressee

Download Address Maintenance Screen

The Download Address Maintenance function displays all addresses which have been downloaded from the central directory but have not been imported to your Con-nect node.

Cmd	CD Name	Node	Alias	Addressee Name	Type	Mail ID	Version
___	DAEFCOC	BOSTON	Dpb	ON	Priv.Cab	ON	1.1
___	DAEFCOC	BOSTON	DpV	BLI	Priv.Cab	BLI	1.1
___	DAEFCOC	BOSTON	D4b	JAS	Priv.Cab	JAS	1.1
___	DAEFCOC	BOSTON	D4d	EDUC	Publ.Cab	EDUC	1.1
___	DAEFCOC	BOSTON	D4k	GBG	Priv.Cab	GBG	1.1
___	DAEFCOC	BOSTON	D4T	BSAC	Shar.Cab	BSAC	1.1
___	DAEFCOC	BOSTON	D4V	DOC	Shar.Cab	DOC	1.1
___	DAEFCOC	BOSTON	D4W	KSC	Priv.Cab	KSC	1.1
___	DAEFCOC	BOSTON	D4Y	KEY	Priv.Cab	KEY	1.1
___	DAEFCOC	BOSTON	D4Z	JPR	Priv.Cab	JPR	1.1
___	DAEFCOC	BOSTON	D4a	Ely,John	Name	JAS	1.1
___	DAEFCOC	BOSTON	D4c	Foraldi,Victor	Name	VF	1.1
___	DAEFCOC	DALLAS	D4j	Ecker,Edith	Name	ECK	1.1

Cmd: Addressee Type _ All Position to CD DAEFCOC_ Node _____
 TO Top DI Display ER Erase IM Import
 Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
 Help Menu Quit ErAll FindA FindN + --
 Mark item(s) from the list above with a command or press a PF-key

CD Name

Name of central directory to which the Con-nect node has uploaded the address.

Node

The transport service node responsible for uploading the address to the central directory.

Alias

A unique ID assigned to each address when uploaded to the central directory.

Addressee Name

Addressee's name which, depending upon the type of addressee, will be one of the following:

Name	User's full name.
Address	Nickname of addressee.
Private Cabinet	Name of private cabinet.
Shared Cabinet	Name of shared cabinet.
Public Cabinet	Name of public cabinet.
Standalone Cabinet	Name of standalone cabinet.
Bulletin Board	Name of bulletin board.
External Node	Name of external address.

Type

Addressee type. The following abbreviations are used:

Name	Addressee is a Con-nect user.
Address	Addressee is a nickname.
Priv.Cab	Addressee is a private cabinet.
Pub.Cab	Addressee is a public cabinet.
Shar.Cab	Addressee is a shared cabinet.
Stnd.Cab	Addressee is a standalone cabinet.
Bulletin	Addressee is a bulletin board.
External	Addressee is an external address.

Mail ID

Identifies the address on the address' originating node. Depending upon the addressee type, the mail ID can be one of the following:

Name	User's Con-nect ID.
Address	Name of cabinet, user, nickname, bulletin board or external address referenced by the nickname.
Cabinet	Name of private, shared, standalone, or public cabinet.
Bulletin Board	Name of bulletin board.
External user	Name of external node.

Version

Version number of the directory synchronization programs which are used by the address' originating Con-nect node.

Addressee Type

You can choose to display all addresses of a particular type. The following abbreviations are used:

- A Display all nicknames.
- B Display all bulletin boards.
- C Display all cabinets - private, public, standalone and shared.
- E Display all external nodes and external addresses.
- N Display all users.
- * Display all addressee types.

Position to CD

Name of the central directory.

Position to Node

You can enter the name of a Con-nect node that interacts with the central directory to display only the addresses on the central directory which originate from that node.

Return to Top of List

To reposition the address list to a specific addressee, you can enter TO in the Cmd column for the addressee and press ENTER. As a result, the selected addressee is now displayed at the top of the list.

Display Additional Address Information

To display the complete address of an addressee, you can enter DI in the Cmd column for the addressee and press ENTER.

```

11:19 AM          * * * C O N - N E C T 3 * * *          14.Feb.94
Cabinet LS          Address Maintenance - ESH          OLAN06

Mail Nickname for
Last Name/Description  Eshberry          Initial  X
First Name            John

Company              Walk America
Title
Department           Public Relations          Number
Location
Address              12004 Sunrise Valley Drive

City                 Reston
Postal Code          20001          Country  USA

Phone                703-WAL-K000          Country Code  1
Extension            25

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP           Menu
Press a PF-key

```

The information displayed here is identical to that which is displayed when a Con-nect user issues the "DISPLAY Address *name*" command.

If you display an external node/address (indicated as External in the Type column), you can press PF4 to display the external address information you provided when you created the external node.

Note:

If the addressee is not an external node or external address, this PF-key is not available.

Erase an Address

To erase an address which has been downloaded, mark the address with ER in the Cmd column and press ENTER. As a result, the address is deleted from the list.

If you want to erase all downloaded addresses, you press PF4 and the following window is displayed:

Cmd	CD Name	Node	Alias	Addressee Name	Type	Mail ID	Version	
---	---	---	---	---	---	---	---	
___	DAEFCOC	+	-----+				b ON	1.1
___	DAEFCOC	!			!	b BLI	1.1	
___	DAEFCOC	!			!	b JAS	1.1	
___	DAEFCOC	!	Erase all Downloaded Addresses		!	b EDUC	1.1	
___	DAEFCOC	!			!	b GBG	1.1	
___	DAEFCOC	!			!	b BSAC	1.1	
___	DAEFCOC	!	73	Addresses will be erased.	!	b DOC	1.1	
___	DAEFCOC	!			!	b KSC	1.1	
___	DAEFCOC	!			!	b KEY	1.1	
___	DAEFCOC	!	Enter Y to confirm: N		!	b JPR	1.1	
___	DAEFCOC	!			!	JAS	1.1	
___	DAEFCOC	!			!	VF	1.1	
___	DAEFCOC	!	Press ENTER to continue		!	ECK	1.1	
---	---	---	---	---	---	---	---	
Cmd:	Address	Type	_ All	Position to CD	DAEFCOC_	Node	_____	
	TO Top	DI Display	ER Erase	IM Import				
Enter-	PF1---	PF2---	PF3---	PF4---	PF5---	PF6---	PF7---	
	PF8---	PF9---	PF10---	PF11---	PF12---			
	Help	Menu	Quit	ErAll	FindA	FindN	+ --	

To confirm the deletions, enter *Y* and press ENTER.

Note:

It is important to remember that PF4 erases *only* the addresses displayed. That means, if you enter a selection criterion such as FHOST in the Node field, press ENTER and then PF4 (erase all), only the cabinets downloaded from node FHOST will be deleted from your local Con-nect node.

Import an Address

You can import addresses on an individual basis directly from the "Download Address Maintenance" screen. To do so, you mark the address with IM in the Cmd column and press ENTER. As a result, a screen similar to the one below displays the address that has been created based upon the addressing rules you specified (see *Add Profiles*). If a unique address cannot be created, you are requested to modify the nickname of the address before importing the address.

Each address which is created with the Import Addresses function is added to the Con-nect node as an external address.

```

 9:36 AM          * * * C O N - N E C T 3 * * *          14.Feb.94
Cabinet LS              Import Address                    OLIN05

Nickname:           Eshberry.John

Folder:             Work                                File:

Central Directory Name: DAEFCOC

Alias:              DnB

Node:               FHOST

Original Mail ID:   ESH

Last Name/Description: Eshberry

First Name:         John

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help Menu Quit Displ Imp                                Canc1
Press PF5 to import address and to continue

```

You can modify the following information:

Nickname

Nickname created for the imported address based upon the import rules you specified with the Add Profile function. See *Add Profiles*.

Folder

Current folder in which the imported address will be stored, as specified with the Add Profile function. See *Add Profiles*.

File

Current file in which imported address will be stored, as specified with the Add Profile function. See *Add Profiles*.

To import the address, press PF5.

Thus the address is imported to your local node and the address is removed from the "Download Address Maintenance" screen.

If, when importing several addresses concurrently, you want to cancel the import of only the currently displayed address, press PF3. If you want to cancel the import of all selected addresses, press PF12.

