

List All Environment Variables

Subroutine Name	Executable Example	Viewable Example
W3LIST-ENVIRONMENT		
W3LIST-ENVIRONMENT-TO-DYNAMIC	E3ENVLIS	E3ENVLIS

Description

List all variables sent by the HTTP server.

Parameters

1. W3LIST-ENVIRONMENT

```

1 W3START          (I4)           /* io/m : Offset to be started at
*                           /*      out: 0 no occurrences
*                           /*      out: >0 more occurrences
1 W3ARRAYCOUNTER   (A72/1:V)     /* io/m : Length of array returned values
1 W3ARRAYNAME       (A250/1:V)    /* o/m : Name of variables
1 W3ARRAYVALUE      (I4/1:V)      /* o/m : Value of variables
1 W3ARRAYVALUELENGTH (L/1:V)      /* o/m : Length of variables
1 W3ARRAYVALUESERVER (I4)        /* o/m : Variable belongs to
1 W3ARRAYMAXIMUM    (*)          /* o/m : Total number of variables

```

2. W3LIST-ENVIRONMENT-TO-DYNAMIC

```

1 W3START          (I4)           /* io/m : Offset to be started at
*                           /*      out: 0 no occurrences
*                           /*      out: >0 more occurrences
1 W3ARRAYCOUNTER   (A/1:V)dynamic /* io/m : Length of array returned values
1 W3ARRAYNAME       (A/1:V)dynamic /* o/m : Name of variables
1 W3ARRAYVALUE      (I4/1:V)      /* o/m : Value of variables
1 W3ARRAYVALUELENGTH (L/1:V)      /* o/m : Length of variables
1 W3ARRAYVALUESERVER (I4)        /* o/m : Variable belongs to
1 W3ARRAYMAXIMUM    (*)          /* o/m : Total number of variables

```

How To Invoke

```

PERFORM W3LIST-ENVIRONMENT W3START W3NAME W3ARRAYCOUNTER
      W3ARRAYNAME(*) W3ARRAYVALUE(*) W3ARRAYVALUELENGTH(*)
      W3ARRAYVALUESERVER(*) W3ARRAYMAXIMUM

```