

Administrators

The installation authorizes the user who is currently logged on to use the System Management Hub and the Entire Screen Builder Administration.

You can authorize other users to administrate the Entire Screen Builder Server. Note that these users must also be authorized for the System Management Hub.

This chapter covers the following topics:

- Overview of Defined Administrators
 - Adding an Administrator
 - Deleting an Administrator
-

Overview of Defined Administrators

When you select the "Administrators" object in the tree-view frame, a list of all products is shown in the detail-view frame.



Expand the object "Entire Screen Builder" (directly below the "Administrators" object). The administrators defined for Entire Screen Builder are now shown. When you select a specific administrator, the detail-view frame shows the products for which this administrator has been registered.

The screenshot is split into two parts. On the left is the tree-view frame, where 'Entire Screen Builder' under 'Administrators' is expanded. It shows two sub-items: 'admin1' (highlighted) and 'mydomain/myname'. Below these are 'System Management Hub', 'Entire Screen Builder', and 'System Management Hub'. At the bottom is 'sunex1'. On the right is the 'Detail Administrator' frame. It has a title bar 'Detail Administrator'. Below it is 'Administrator admin1' with a small icon. Underneath is the text 'Registered for the following product(s):'. Below that is a table with two columns: 'Icon' and 'Product'.

Icon	Product
	Entire Screen Builder
	System Management Hub

Adding an Administrator

You do not have to stop the Entire Screen Builder Server. You can also add administrators when the server is running.

▶ To add an administrator

1. In the tree-view frame, select the "Administrators" object (i.e. the name next to the plus sign).
2. In the command frame, choose the **Add Administrator** button.

The Add Administrator dialog appears.

Icon	Product	Administrator
	Entire Screen Builder	<input type="checkbox"/>
	System Management Hub	<input type="checkbox"/>

3. Specify the name of the user that you want to add. The user must be one of the following:
 - A known user on the local node.
 - A known user in a domain. In this case, you have to specify the domain name with the user ID:

domain-name/user-name

4. Select the **Administrator** check boxes for Entire Screen Builder and for the System Management Hub.

In order to administrate Entire Screen Builder, a user must also be authorized for the System Management Hub.

5. Choose the **OK** button.

A message is now shown in the detail-view frame, indicating that the defined user has been processed to be added for the selected products.

6. Choose the **Close** button.


Deleting an Administrator

You do not have to stop the Entire Screen Builder Server. You can also delete administrators when the server is running.

▶ To delete an administrator

1. In the tree-view frame, expand the "Administrators" object.
2. In the tree-view frame, expand the "Entire Screen Builder" object.
3. Select the administrator that is to be deleted.
4. In the command frame, choose the **Delete Administrator** button.

The Delete Administrator dialog appears.



5. Select the **Delete** check box(es) for the product(s) for which the administrator is to be deleted.
6. Choose the **OK** button to confirm the deletion.

A message is now shown in the detail-view frame, indicating that the user has been deleted as an administrator for the selected products.

7. Choose the **Close** button.