

# Mass Deletion of Active Conditions

This function allows the mass deletion of active Conditions. You may use several selection criteria for the active conditions to be deleted.

Please check carefully the side effects of a mass deletion, before you perform it.

This section covers the following topics:

- Invoking the Mass Deletion of Active Conditions
- Field Descriptions: Active Condition Deletion

## Invoking the Mass Deletion of Active Conditions

 **To invoke the Active Condition Maintenance facility**

- Press PF6 (Delete) from the Active Conditions screen.

The Active Condition Deletion window opens:

```

23.01.02                *** Entire Operations 4.1.1 ***                14:38:37
Owner SN                Active Conditions
-----
Cmd Owner      Network  Condition      Date      Time  Run  Status
SN*-----*-----*-----
_ SN          BS2-EX-2  JOB-1-OK      27.08.02  16:20  1108 free
_ SN          BS2-EX-2  JOB-1-OK      27.08.02  16:21  1109 free
_ SN          BS2-EX-2  JOB-1-OK      27.08.02  16:21  1110 free
_ SN          +-----+ 2 00:07  1111 free
_ SN          !                ! 2 16:22  1108 free
_ SN          !                Active Condition Deletion      ! 2 16:22  1109 free
_ SN          !                ! 2 16:22  1110 free
_ SN          !  Owner      ==> _____ ! 2 00:08  1111 free
_ SN          !  Run from  ==> _____ ! 2 16:23  1110 free
_ SN          !    to      ==> _____ ! 2 00:08  1111 free
_ SN          !  Confirm? ==> Y          ! 2 08:12  1400 free
***** !                ! *****
D Delete !                !
Command !  Enter-PF1---PF3----- ! _____
Enter-PF1 !                ! F9---PF10--PF11--PF12---
Hel +-----+ Menu
    
```

This screen displays a list of all active conditions belonging to your owner.

You can modify, add or delete active conditions.

## Field Descriptions: Active Condition Deletion

The following table explains the fields on the Active Condition Deletion window:

<b>Field</b>	<b>Description</b>
Owner	Owner of the conditions. Wildcard may be used.
Network	Network the conditions. Wildcard may be used.
Condition	Condition(s). Wildcard may be used.
Run from	Start of run number interval to be deleted.
Run to	End of run number interval to be deleted.
Confirm	<b>Y</b> Prompt for each deletion. <b>N</b> Perform deletions without prompting.