

INPL

- For Mainframes
- For UNIX/OpenVMS
- For Windows

INPL for Mainframes

INPL [R]

If you enter the INPL command without any parameters, the INPL utility will be invoked. This utility is **only** used for the loading of Software AG installation datasets into the system files as described in the Natural INPL Utility documentation.

Apart from that, you use the utility NATLOAD to load objects into the system files.

The INPL functions used for the installation are described in the INPL online help. Apart from that, the INPL command provides the following special function:

INPL R - Natural Security Recover

This option is only available if Natural Security is installed.

"INPL R" is used to reset the access to the Natural Security library SYSSEC to its original status.

If you issue "INPL R", the user DBA, the library SYSSEC, and the link between the two will be redefined as after the initial installation, while all other links to SYSSEC will be cancelled. See also Inaccessible Security Profiles in the section Countersignatures of the Natural Security documentation.

INPL for UNIX/OpenVMS

INPL [R]

If you enter the INPL command without any parameters, the INPL utility will be invoked. This utility is *only* used for the loading of Software AG installation datasets into the file system as part of the installation process (as described in the Setup and Installation of Natural under UNIX or Installing and Setting Up Natural on OpenVMS Documentation).

Apart from that, you use the utility NATLOAD in library SYSUNLD to load objects into the file system.

In addition, the INPL command provides the following special function:

INPL R - Natural Security Recover

This option is only available if Natural Security is installed.

"INPL R" is used to reset the access to the Natural Security library "SYSSEC" to its original status.

If you issue "INPL R", the user "DBA", the library "SYSSEC", and the link between the two will be redefined as after the initial installation, while all other links to "SYSSEC" will be cancelled. See also Inaccessible Security Profiles in the section Countersignatures of the Natural Security documentation.

INPL for Windows

INPL [R]

If you enter the INPL command without any parameters, the INPL utility will be invoked. This utility is *only* used for the loading of Software AG installation datasets into the file system as part of the installation process (as described in your Natural Installation Guide and the INPL Utility documentation).

Apart from that, you use the utility SYSPAUL (which is described in the Natural Operations documentation) to load objects into the file system.

In addition, the INPL command provides the following special function:

INPL R - Natural Security Recover

Note:

This option is only available if Natural Security is installed.

"INPL R" is used to reset the access to the Natural Security library "SYSSEC" to its original status.

If you issue "INPL R", the user "DBA", the library "SYSSEC", and the link between the two will be redefined as after the initial installation, while all other links to "SYSSEC" will be cancelled. See also Inaccessible Security Profiles in the section Countersignatures of the Natural Security documentation.