

Storagespace Maintenance Menu

The Storagespace Maintenance menu is called with function code M and object code SC in a Predict main menu or the command MAINTAIN STORAGESPACE.

10:22:43	***** P R E D I C T 4.2.2 *****	2002-07-31
Plan 0	- (SC) Storagespace Maintenance -	Profile HNO
Function		Function
A Add a storagespace		D Display storagespace
C Copy storagespace		L Link children
M Modify storagespace		O Edit owners of a storagespace
N Rename storagespace		S Select storagespace from a list
P Purge storagespace		W Edit description of a storagespace
Function		
Storagespace ID ..		Association
Copy ID		
Restrictions* Profile HNO,used		Association*
Command ==>		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---		
Help Next Stop Last LnkEl Flip Print Impl AdmFi SelFi Prof Main		

Note:

Parameters not listed here are described under Global Attributes.

Parameters	
Function	Standard maintenance functions are described in the section Maintenance in the Predict Reference documentation . Function Purge is described under Storagespace-Specific Maintenance

Add a Storagespace Screen

The screen is displayed for the Add a Storagespace function. The Copy and Modify screens are similar.

```

10:26:41          ***** P R E D I C T 4.2.2 *****
                     - Add a Storagespace -
Storagespace .... HNO-SC

Keys ..           Zoom: N

Storagespace attributes
Storagegroup name ....
VSAM catalog name ....
Device type .....

Abstract      Zoom: N      Volumes
               1
               7
              13
              19
              25
              31
              37
              43
              49
              55

EDIT:   Owner: N   Desc: N      MORE Volumes: N

```

Note:

Parameters not listed here are described under Global Attributes.

Parameters	
Storagespace	ID of the Predict storagespace object.
Storagespace attributes	
Storagegroup name	Name of the storagegroup in DB2.
VSAM catalog name	Name or alias of an ICF catalog. Aliases are used for names of ICF catalogs that are longer than eight characters.
Device type	For documentation purposes.
Volumes	Physical volume(s) where the storagespace resides. Up to 60 volumes can be entered here. Specify MORE volumes=Y to specify up to 140 volumes.

Storagespace-Specific Maintenance

Purge Storagespace - Code P

The following restriction applies to this function:

- A storagespace cannot be deleted if it is still referenced by a database, a dataspace or a file.

Otherwise this function behaves as described in the section Maintenance in the **Predict Reference documentation**.