

Operator Command Overview

The following table summarizes the Com-plete operator commands:

Command	Purpose
ACCESS	Allows the operator to start or shutdown the ACCESS interface.
ALLOW	Enables the computer operator to allow use of the following Com-plete facilities by terminal users: remote job entry and ULOG ON functions.
CANCEL	Enables the computer operator to terminate an online application program abnormally.
CLOSE	Causes the current Com-plete capture data set to be closed, and, therefore, available for access by batch jobs.
COMSEC	Allows the computer operator to issue Com-plete SECURITY commands (only available if Com-plete SECURITY is installed).
DCTRL	Allows the computer operator to display and monitor terminals with control status in the Com-plete network.
DISALLO	Enables the computer operator to disallow use of the following facilities by terminal users: remote job entry and ULOG ON functions.
DTASKS	Displays the status of all Com-plete tasks (including the threads) and batch jobs using Com-plete functions.
DUMP	VSE: switches destination device for Com-plete dumps from SYSLST to COMDMP and vice versa.
ENQ	Displays a selection of or all outstanding ENQs from Com-plete's threads.
EOJ	Causes a logical shutdown to occur for the Com-plete system.
FORCE	Enables the computer operator to force a terminal or user from the Com-plete system.
HMSG	Causes Com-plete to reissue the message Com-plete IS NOW OPERATIONAL to all or selected terminals.
IGNORE	Causes immediate termination of terminal I/O for one or more terminals, lines, or user IDs. If a user is logged on, and the IGNORE command is entered for the user's terminal or user ID, the user is logged off from the terminal.
LOGOFF	Logs off one or more terminals or users.
MSG	Sends a message to one or more terminals or users.
PGM	Enables the computer operator to load, delete, or refresh RESIDENTPAGE modules.
PLIST	Displays a list of the current tasks defined in the requested task group and the status of each.
QOVER	Displays a list of the current queues defined in the system and the status of each.

Command	Purpose
QUIESCE	Causes Com-plete's VTAM application to quiesce.
RESTART	Restarts terminal I/O for one or more terminals or lines.
SERV	Enables a server to be stopped or started.
SETCTL	Enables the computer operator to dynamically set a designated terminal to control or privileged status, allowing it to perform functions not normally permitted.
STATS	Writes the current Com-plete statistics to the sysout data set.
STOP	Synonym for the EOJ command.
TASKS	Attaches additional operating system tasks in a Com-plete task group or to detach some of the tasks of a task group.
TLIST	Displays a list of the current threads defined in the requested thread group and the status of each.
UNCTL	Enables the computer operator to remove control status from a specified terminal.
USER	Enables a user program to be attached with or without data. A special parameter, UFILE, allows the operator to change the status of a file.
UU	Allows the display of information about one or more active users.
VTAM	Allows the computer operator to perform certain functions on the Com-plete VTAM interface.