

Export to Entire Operations Viewer

(version 1.x.x only, file format *.eov)

Entire Operations Viewer versions later than v1.x.x use "standard" Entire Operations export files as input.

This section covers the following topics:

- Export Procedure
- Export Targets

Export Procedure

If you select 'Export to EOR Viewer' (*.eov only) in the Import / Export Main Menu, you must select first the objects to be exported:

```

20.11.01      *** Entire Operations Import/Export Utility ***      16:33:24
              +-----+ SN
              !
----- !
Option ==> 4 ! Viewer Export Selection !
              !
              !           Owner   ==> example__ !
              !           Network ==> e60-flow__ !
              1 !
              2 !
              3 ! PF3 End !
              4 +-----+

```

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
 Help End

If you want to return, use PF3. Otherwise press Enter to continue to the next screen:

```

20.11.01      *** Entire Operations Import/Export Utility ***      16:33:24
              +-----+-----+ SN
              !
Option ==> 4  ! Viewer Export Selection                             !
              !
              !           Owner   ==>  example___                !
              !           Network ==>  e60-flow___                !
              !
              !           PF3   End                                !
              !
              !           +-----+
              !           !
              !           ! Please select the Export Target      !
              !           !
              !           !   _ Screen                            !
              !           !   _ Natural Printer 1                 !
              !           !   _ Natural Printer 2                 !
              !           !   X Entire Connection (workfile 7)    !
              !           !   _ Workfile 1                         !
              !           !
              !           ! PF1 Help                                !
Enter-PF1---PF +-----+ PF10--PF11--PF12---
              Help      End
    
```

Export Targets

If you have selected a network, you will be prompted for an export target:

| | |
|---------------------------------------|--|
| Screen | To display the export file format online. |
| Natural Printer 1, 2 | You must define one of these printers before you use this option. |
| Entire Connection (workfile 7) | You can export directly to a PC file with this option. Note: If you use Entire Operations Viewer v1.x.x, the PC file must be named "*.eov". |
| Natural Workfile 1 | You must define a workfile before you can use this option. |

For more detailed information, see the **Entire Operations Viewer online help**.