

Entire Operations Logon Screen

The startup procedure of Entire Operations is defined specifically for your installation: ask your System administrator.

Having started Entire Operations, the Entire Operations Logon screen appears:

```

20/11/01                                     10:05:33
=====
          EEEEEEE  NNN  NN  TTTTTTTT  II  RRRRRRRR  EEEEEEE
          EE        NNNN NN   TT      II  RR   RR   EE
          EE        NN NN NN   TT      II  RR   RR   EE
          EEEEEEE  NN  NNNN   TT      II  RRRRRRRR  EEEEEEE
          EE        NN  NNN   TT      II  RR   RR   EE
          EEEEEEE  NN  NN   TT      II  RR   RR   EEEEEEE

          OOOOOO  PPPPPP  EEEEEEE  RRRRRR  AAAAAA  TTTTTTTT  II  OOOOOO  NN  NN  SSSSS
          OO  OO  PP  PP  EE        RR  RR  AA  AA   TT  II  OO  OO  NNN  NN  SS
          OO  OO  PP  PP  EE        RR  RR  AA  AA   TT  II  OO  OO  NN  N  NN  SS
          OO  OO  PPPPPP  EEEEEEE  RRRRRR  AAAAAA   TT  II  OO  OO  NN  NNN  SSSSS
          OO  OO  PP      EE        RR  RR  AA  AA   TT  II  OO  OO  NN  NN   SS
          OOOOOO  PP      EEEEEEE  RR  RR  AA  AA   TT  II  OOOOOO  NN  NN  SSSSS
=====

          Userid ====> GHH_____
          Password ====>

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
          Help           End

```

Note:

If you are already logged on to Natural Security and your user ID is defined in Entire Operations, the above Logon screen is bypassed and you are presented with the Main Menu. However, display of the Logon screen can be forced by an appropriate setting in the Entire Operations defaults.

If you wish to work in Entire Operations with a different user ID, you must change the STACK statement in your startup procedure to reflect the desired user ID (for example, STACK=(LOGON SYSEOR;NATOP user ID). If in doubt, ask your system programmer.

The input fields on the Logon screen have the following meaning:

Field	Description
Userid	By default, your TP environment user ID appears in this field. You can enter Entire Operations under a different user ID by overtyping the default value. Any user ID entered in this field must be defined to Entire Operations. In addition, the User ID entered here must belong to the same owner as the User ID which appears here by default. For more information on the concept owner, see the subsection Owner in this documentation and the subsection User Maintenance in the section System Administrator Services of the Entire Operations Administration Documentation. If the User ID of your TP environment is not defined in Entire Operations, you cannot work with the product. The message is displayed EOR0009: INIT USER is unknown to Entire Operations.
Password	Enter the password associated with the user ID you entered in the Userid field. The password is meaningful if security systems such as RACF or ACF2 are used. To enter hexadecimal passwords (for OS/390 and BS2000/OSD): H'xx xx xx xx or X'xx xx xx xx where xx xx xx xx is a hexadecimal string. The maximum length is 16 characters, or 8 bytes.

If necessary:

1. Correct your user ID.
2. Enter your Password.
3. Press Enter to display the Entire Operations Main Menu.

If you do not enter your password correctly, it is prompted again in a window:

```

20/11/01                                     10:06:53
=====
          EEEEEEE  NNN  NN  TTTTTTTT  II  RRRRRRRR  EEEEEEE
          EE        NNNN NN   TT      II  RR   RR   EE
          EE        NN NN NN   TT      II  RR   RR   EE
          EEEEEEE  NN  NNNN   TT      II  RRRRRRRR  EEEEEEE
          EE        NN  NNN   TT      II  RR   RR   EE
          EEEEEEE  NN   NN   TT      II  RR   RR   EEEEEEE

          +-----+
          OOOOOO  PPPPP ! EOR0004 - Please enter Password !OOOO NN  NN  SSSSS
          OO  OO  PP  PP !                                ! OO  NNN NN  SS
          OO  OO  PP  PP !           ENTIRE OPERATIONS    !OO  NN N NN  SS
          OO  OO  PPPPPP !           ENTIRE SYSTEM SERVER Logon !O  NN  NNN  SSSSS
          OO  OO  PP      E !                                !  NN  NN  SS
          OOOOOO  PP      EE ! Node      ==> 146 EOR NODE MVS/XA ! NN  NN  SSSSS
          ===== ! Userid      ==> GHH_____ !=====
          ! Password ==>                                !
          Userid ==> GHH !                                !
          Password ==> ! PF3 End                            !
          +-----+
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
          Help      End
    
```

1. Enter your correct Password.
2. Press Enter to display the Entire Operations Main Menu.