

Restrictions

This subsection covers the following topics:

- Prerequisites
 - Listing All Active Jobs
 - Column Headings
 - Line Commands
 - Special PF Keys
-

Prerequisites

If the user is of type **A** (Administrator), or if the user has access to the owner SYSDBA, then all active jobs are displayed.

In all other cases, the following active jobs are displayed:

- from networks of the current owner
- from networks of owners, to which the user has access
- from networks, for which the user has been granted access (see Authorizing Other Users to Access a Network) in the section Network Maintenance.

Listing All Active Jobs

- According to Owner, Network and Job
- According to Submit User ID
- According to Status

According to Owner, Network and Job

You can list active jobs for selected Owner(s), Network(s) and/or Job name(s).

Use an asterisk * as a wildcard to enter selection criteria in the fields preceded by an asterisk * directly below the respective column headings.

Press Enter to list the active jobs which satisfy the selection criteria.

According to Submit User ID

Enter a Submit Userid in the field in the upper right-hand corner of the screen and press Enter to list only those active jobs with the selected Submit User ID.

The entered Submit Userid is **not** converted in capital letters. The exact spelling is required. Thus, UNIX and Windows userids can be entered as well.

According to Status

See the subsection Listing Active Job Status in the section Maintaining Active Jobs.

Column Headings

The following table explains the column headings for the data listed on the Active Jobs screen:

| Column | Description |
|---------|--|
| C | One-character line command input field. For possible values, see Line Commands: Active Jobs in the section Maintaining Active Jobs. |
| Owner | The network owner. Use an asterisk * as a wildcard for entering selection criteria. |
| Network | The network to which the job belongs. Use an asterisk * as a wildcard for entering selection criteria. |
| Job | The job name as defined to Entire Operations. Use an asterisk * as a wildcard for entering selection criteria. Lines referring to a network run are identified by a "-" in this field. |
| Run | Job run number automatically assigned at activation time. Together with the job name, the job run number uniquely identifies an active copy of a job. |
| JobId | Job identifier as assigned by the operating system or by the job entry subsystem. |
| Time | Last action or check time for the job. |
| Message | Last message issued for the job by Entire Operations. Press <PF11> (Right) or <PF10> (Left) to display the full message text. For a list of possible messages and their meaning, see Messages in Active Job Display. |

Line Commands

For a description of the available line commands, see Line Commands: Active Jobs.

Note:

Most of these line commands refer to a specific job and may therefore not be used in lines referring to network runs. For these lines, only the commands **D** and **A** are allowed.

Special PF Keys

For a description of available PF keys, see Special PF Keys: Active Jobs.