

Terminal Command List

The following table provides an overview of the terminal commands and the functions they perform.

Command	Function
%	Continuation indicator for INPUT statements in batch programs.
%%, %.	Interrupt current Natural operation.
%*	Disable display of input characters. In batch mode, suppress printing of next input record read.
%.P	Delete first entry from stack.
%.S	Read stack entry without deleting it.
%/	Forces end-of-file condition when using INPUT statement in batch mode.
%?	Invoke help information for terminal commands.
%.+, %.-	Enable/disable use of Natural Connection.
%<TECH	Display technical information.
%<TEST	Invoke the Natural Debugger.
%=	Assign colors to fields.
%A	Play back a recording.
%B	Activate/deactivate a recording.
%B=	Specify library for a recording.
%C	Copy current screen into Natural source area.
%CC, %CS	Copy data to the stack or into the system variable *COM.
%D	Activate keyword/delimiter mode.
%D=	Control of outlining.
%DUE	Dump for specific error.
%E	Display screen captures.
%E=	Activate/deactivate error processing.
%F	Activate forms/screen mode.
%F=	Frame characters for window.
%FM	Activate/deactivate edit mask free mode.
%G	Set playback mode for a recording.
%H	Produce hardcopy output.
%I	Capture current screen.
%J	Invoke help routine.
%KN, %KO, %KS	Function-key logic for Siemens terminals.
%K_{nn}, %KP_n	Simulate PF- and PA-keys.
%L	Disable lower- to upper-case translation.

Command	Function
%L=	Set language code.
%M	Control of message line.
%MSGSF	Display system error messages in full.
%N	Activate non-conversational mode.
%O	Deactivate screen capturing.
%P	Capture screen sequence.
%P=	CALL options.
%Q	Suppress map printing in batch mode.
%QO	Suppress pseudo-conversational output.
%QS	Simultaneous output of multiple screens.
%R	Repeat INPUT statement.
%RM	Protection of light pen sensitive fields.
%RN	Suppress compression of screen data.
%RO	Activate/deactivate screen optimization.
%S	Resume screen capturing.
%T	Position cursor on top of screen.
%Tll/cc	Set cursor position.
%T+ and %T-	Position cursor on protected field.
%T*	Position cursor outside window.
%T=	Activate converter routine for specific device type.
%TRE	Activate/deactivate external trace.
%TRI	Activate/deactivate internal trace.
%U	Enable lower- to upper-case translation.
%V	Control of print mode.
%W	Natural window handling.
%X	Control of statistics line/infoline.
%Y	Control of PF-key lines.
%Z	Clear source area.