

Object Handler - Advanced User

This section describes how to invoke advanced-user mode and perform the unload, load and scan functions.

- Activating Advanced User
 - Processing Objects
-

Activating Advanced User

To activate advanced-user mode

- On the Natural Object Handler Main Menu, select the "Advanced user" field (the field is not selected by default).
Or, in the SYSOBJH profile, set Advanced-Mode to **Y** (Yes). See also SYSOBJH Profile.

Processing Objects

To process objects in advanced-user mode

1. On the Natural Object Handler Main Menu, check the "Advanced user" field and select Unload, Load or Scan.
2. Press ENTER to continue.
The Unload/Load/Scan Settings screen appears with the sections Options and Parameters.
3. Set the options and parameters as described in the section Settings.
4. Press ENTER to continue.
The Select Unload/Load/Scan Type screen appears.
5. Select the objects you want to process: see also the section Object Specification.
6. Choose Details to specify additional selection criteria: see the relevant sections in Object Specification.
7. Press ENTER to continue.
 - If the parameter "Display-Cmd-in-Advanced-Mode" is set to N (No) in the SYSOBJH profile (this is the default), or if no such profile exists, the command generated from the input data is executed immediately after you have specified the selection data. See SYSOBJH profile.
The Display Unload/Load/Scan Report screen appears with a list of the objects processed if the parameter Write Report was selected (this is the default). See also Work File Options in the section Settings.
 - If the parameter "Display-Cmd-in-Advanced-Mode" is set to Y (Yes) in the SYSOBJH profile (see the relevant section), or if the internal command SET ADVANCEDCMD ON (see Commands for CUIs) was executed earlier, a screen appears displaying the command generated from the input data.
You can save the command displayed as a Workplan of the type PROCEDURE (see also Workplans), by entering the command SAVE or by choosing PF5/Save.
Press ENTER to confirm the command execution or choose PF3/Exit to modify the processing settings before confirming the command execution.
The Display Unload/Load/Scan Report screen appears with a list of the objects processed if the parameter Write Report was selected (this is the default). See also Work File Options in the section Settings.