

Natural System Error Message Selection

This function is used to list and select Natural system error messages.

The instructions below show how to invoke and execute the function by using advanced-user mode (see the relevant section):

To list and select Natural System error messages

- On the Unload Natural System Error Messages screen, choose "Select system error messages" and press ENTER.
The List System Error Messages screen appears with a list of all system error messages for the Natural system file specified.
- If you want to unload one or more objects, select a system error message or specify a range: see Columns and Commands below.
- Press ENTER.
The object(s) has been added to the list of unload items.
- Choose PF2/Unloa to execute the unload function (see also Columns and Commands below).

Columns and Commands

The List System Error Messages screen provides the following columns and commands:

Column	PF Key	Explanation
Cmd		<p>The following line commands can be entered in the input field next to the object desired:</p> <p>L or LI Lists the error message.</p> <p>S, SE, U or UL Only applies to the unload function. Selects the error message for subsequent unloading.</p> <p>DE Deletes the error message.</p> <p>DL Deletes the long text of the error message only.</p>
Number		<p>Lists all Natural system error messages available and provides the option to enter a range of error messages in the input fields of the first row. Valid ranges for selection are:</p> <p><i>value*</i> All items with names that begin with value.</p> <p><i>value></i> All items with names greater than or equal to value. Example: 10></p> <p><i>value<</i> All items with names less than or equal to value. Example: 100<</p>

Column	PF Key	Explanation
S/L-Kind		The kind of error message text: S Short texts of error messages. L Long texts. A All short and/or long texts.
Language		The language code(s) of the error messages to be selected: Up to 8 valid Natural language codes. Asterisk (*) selects all language codes.
Error Message Text		Displays the short text of the error message.
	PF2	Only applies to the unload function. Starts unloading the object(s) selected for processing. As an alternative, in the command line, enter either of the following direct commands: UNLOAD UNLD
	PF6	Goes to the top of the list.
	PF7	Returns to the previous page.
	PF8	Goes to the next page.
	PF9	Goes to bottom of the list.
	PF11	Selects all objects of the range(s) specified. As an alternative, in the command line, enter the following direct command: <u>SELECT ALL</u> .