

# Object Handler - Advanced User

This section describes how to invoke the Advanced-user mode and how to perform the unload, load and scan functions.

- Activating Advanced User
  - Processing Objects
- 

## Activating Advanced User

### ▶ To activate the Advanced-user mode

- Check the "Advanced user" field on the **Natural Object Handler Main Menu** (the default is unchecked). Or, in the SYSOBJH profile, set Advanced-Mode to **Y** (Yes). See also SYSOBJH Profile.

## Processing Objects

### ▶ To process objects in Advanced-user mode

1. On the **Natural Object Handler Main Menu**, check the "Advanced user" field and select Unload, Load or Scan.
2. Choose ENTER to continue.  
The Settings window appears providing the sections Options and Parameters.
3. Set the options and parameters as described in the section Settings.
4. Choose ENTER to continue.  
The Select Unload/Load/Scan Type screen appears.
5. Select the objects you want to process: see also the section Object Specification.
6. Choose Details to specify additional selection criteria: see the relevant sections in Object Specification.
7. Choose ENTER to continue.
  - If the parameter "Display-Cmd-in-Advanced-Mode" is set to N (No) in the SYSOBJH profile (this is the default), or if no such profile exists, the command generated from the input data is executed immediately after you have specified the selection data. See SYSOBJH profile.  
The Display Unload/Load/Scan Report screen appears listing the objects processed if the parameter Write Report was selected (this is the default). See also Work File Options in the section Settings.
  - If the parameter "Display-Cmd-in-Advanced-Mode" is set to Y (Yes) in the SYSOBJH profile (see the relevant section), **or if the internal command SET ADVANCEDCMD ON (see Commands for CUIs) was executed earlier**, a screen appears displaying the command generated from the input data.  
You **can** save the command displayed as a Workplan of the type PROCEDURE (see also Workplans), by entering the command SAVE or by choosing PF5/Save.  
Choose ENTER to confirm the command execution or choose PF3/Exit to modify the processing settings before confirming the command execution.  
The Display Unload/Load/Scan Report screen appears listing the objects processed if the parameter Write Report was selected (this is the default). See also Work File Options in the section Settings.