

# Report Listing

Objects of type report listing log

- a transfer operation of the Predict Coordinator, or
- a conversion operation.

Report listings are added automatically with an ID assigned by the system. For this reason, the functions Add and Copy are not available for this object type.

In the predefined Predict metastructure, a report listing can have passive and active associations of the following types:

Valid passive association: *no predefined association*

Valid active association: Extract (default active association *Uses ET*)

When transferring data with the Predict coordinator, the extract containing the objects to be transferred is automatically linked as a child to the report listing.

See the Predict Coordinator documentation for more information.



This section covers the following topics:

- Report Listing Maintenance Menu
- Report Listing Retrieval

---

## Report Listing Maintenance Menu

This menu is called with function code M and object code RT in a Predict main menu or with the command MAINTAIN REPORTLISTING.

```
13:24:44          ***** P R E D I C T 4.3.1 *****          2003-05-31
Plan 0          - (RT) Report listing Maintenance -          Profile HNO

Function                                Function

M Modify Report listing                D Display Report listing
N Rename Report Listing                L Link children
P Purge Report listing                 S Select Report listing from list

Function .....

Report listing ID .....                Attributes ....*

Restrictions .....*   Profile HNO,used   Association ...*

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help Next Stop Last LnkEl Flip Print Impl AdmFi SelFi Prof Main
```

**Note:**  
Parameters not listed here are described under Global Attributes.

Parameters			
Function	Enter one of the codes in the menu to execute one of the functions. These functions are described in the section Maintenance in the <b>Predict Reference documentation</b> .  <b>Note:</b> As report listings are added automatically with an ID which is assigned by the system, the functions Add and Copy are not available for this object type.		
Report Listing ID	ID of the report listing object. This ID is assigned automatically when the object is added and is composed as follows:		
	USR	TYP	199940803
	User ID	Subtype	Date
	The ID of the user who performed the coordinator function. In batch mode: the job name. This section is appended by underscore characters if less than 8 characters.	One of the following: <ul style="list-style-type: none"> <li>● EXP Export</li> <li>● IMP Import</li> <li>● CON Conversion</li> <li>● TRC Trace</li> <li>● UNL Unload</li> <li>● LOA Load</li> <li>● ALF* ALF to Migrate conversion</li> <li>● MIG* Migrate to ALF conversion</li> </ul> * <b>Note:</b> Report listings of type ALF and MIG are no longer created with this version but objects of this type may exist from earlier versions.	Date on which the report listing was added.  Format YYYYMMDD
			1522453
			Time
			The time at which the report listing was added.  Format HHMSST.

### Modify Report Listing Screen

```

13:35:13          ***** P R E D I C T 4.3.1 *****          2003-05-31
                    - Modify Report listing -
Report listing .. HNO-RT          Added 2003-05-31 at 13:25
                                   by HNO
Keys ..          Zoom: N

Attributes
Subtype ..... Export

Processing

Abstract          Zoom: N
    
```

**Note:**  
Parameters not listed here are described under Global Attributes.

<b>Explanation</b>	
Added by	The function with which the report listing was added. The user who created the report listing can be seen in the first eight characters of the report listing ID.
Subtype	Subtype of report listing. <ul style="list-style-type: none"> <li>● Conversion (ALF to Migrate or Migrate to ALF conversion)</li> <li>● Export</li> <li>● Import</li> <li>● Trace</li> <li>● Load</li> <li>● Unload</li> </ul>
<b>Processing</b>	
Exported / Not Exported	For the function Export: The number of objects successfully exported / objects not exported due to errors. <p><b>Note:</b> See the extended description of the report listing for a complete list of these objects.</p>
Loaded / Replaced / Not Loaded	For the function Import: The number of new objects successfully loaded / existing objects overwritten / objects not loaded due to errors. <p><b>Note:</b> See the extended description of the report listing for a complete list of these objects.</p>

## Report Listing Retrieval

Information on report listings is retrieved using standard retrieval functions. These functions are described in the section Retrieval in the **Predict Reference documentation**.

### Layout of Report Listing Lists

```

13:01:24          ***** P R E D I C T 4.3.1 *****          2003-05-31
                    - List Report listing -

-----
Cnt  Report listing ID          Subtype
1235 FH_____ -EXP-19950213-1133434  Export
1236 FH_____ -EXP-19950213-1134044  Export
1237 FH_____ -IMP-19950213-1135086  Import
1238 FH_____ -IMP-19950213-1750037  Import
1239 FH_____ -IMP-19950213-1758171  Import
1240 FH_____ -MIG-19950209-1531474  Convert
1241 GER-RT          Import
1242 GER_____ -ALF-19950206-1017009  Convert
    
```

### Output Options for Report Listing Retrieval

The output options valid for this object type are identical to those for object type dataspace. See Output Options for Dataspace Retrieval.