

Interface

This section covers the following topics:

- Interface Maintenance
 - Interface Retrieval
-

Interface Maintenance

The Interface Maintenance Menu is called with the command MAINTAIN INTERFACE.

Overview of Functions and Commands

Function	Code	Command
Add an interface	A	ADD INTERFACE
Copy interface	C	COPY INTERFACE
Modify interface	M	MODIFY INTERFACE
Rename interface	N	RENAME INTERFACE
Purge interface	P	PURGE INTERFACE
Display interface	D	DISPLAY INTERFACE
Link children	L	LINK INTERFACE <active-association-type>
Edit owners of an interface	O	EDIT INTERFACE OWNER
Select interface from a list	S	SELECT INTERFACE
Edit description of an interface	W	EDIT INTERFACE DESCRIPTION

Parameters

Interface	Field	Position
ID	Interface ID	1
<>	Copy ID	2

Interface-specific Maintenance Commands

Interface objects are processed using Standard Maintenance Commands.

Interface Retrieval

The Interface Retrieval Menu is called with the command RETRIEVE INTERFACE.

Overview of Functions and Commands

Retrieval Type	Code	Default Output Mode	Command
Interfaces	D	D	DISPLAY INTERFACE
		L	LIST INTERFACE
		S	SELECT INTERFACE
		D	SHOW INTERFACE
Execute retrieval model	E	T	EXECMODEL INTERFACE
Dummy/Placeholder interfaces	C	L	DUMMY INTERFACE <passive-association-type>
Interfaces with parents	B	D	PARENTS INTERFACE <passive-association-type>
Interfaces with no parent	O	L	FREE INTERFACE ANY ALL <passive-association-type>
Interfaces with children	T	D	CHILDREN INTERFACE <active-association-type>
Interfaces with no child	U	L	EMPTY INTERFACE ANY ALL <active-association-type>

Parameters

Keyword	Field	Position
ID	Interface ID	1
RES	Restrictions	2
OUT	Output options	3
MODEL	Model	4
MODE	Output mode	5

Interface-specific Retrieval Commands

See also Standard Retrieval Commands.