



# **SYSTEMS MANAGEMENT**

---

## **Entire Operations Viewer**

Version 2.1.1



**Order Number: EO211-008WIN**

This document applies to Version 2.1.1 of Entire Operations Viewer. Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

© March 2002, Software AG  
All rights reserved

Software AG and/or all Software AG products are either trademarks or registered trademarks of Software AG. Other products and company names mentioned herein may be the trademarks of their respective owners.

# Table of Contents

- Release Notes - Overview** . . . . . 1
- Release Notes - Overview . . . . . 1
- Release Notes and Installation** . . . . . 2
- Release Notes and Installation . . . . . 2
- Introduction . . . . . 2
- New Features . . . . . 2
- Installation . . . . . 2
- System Prerequisites . . . . . 2
- Installation Procedure . . . . . 3



# Release Notes - Overview

This documentation covers the following topics:

-  **Release Notes** Provides information on new features and describes the procedure to install Entire Operations Viewer.

# Release Notes and Installation

This documentation covers the following topics:

- Introduction
  - New Features
  - Installation
- 

## Introduction

Entire Operations Viewer has been completely revised for Version 2.1.1. The main motivation was to provide offline viewing of Entire Operations data. Unlike the previous version, Entire Operations Viewer Version 2.1.1 uses the standard export format of Entire Operations. Using FTP or Software AG's Entire Connection, you can import single Entire Operations objects or the whole Entire Operations environment to the Entire Operations Viewer on your PC. You can then explore your job networks and related information using the graphical user interface.

The Entire Operations Viewer Version 2.1.1 runs under Microsoft Windows (TM) 32-bit platforms.

## New Features

- State-of-the-art user interface for exploring Entire Operations data.
- Improved display of Job Network Graphics, including free positioning and saving in different file formats.
- Support for the following Entire Operations master objects: Calendars, Descriptions, End of Job checks, Jobs, Mailboxes, Networks, Nodes, Schedules, Symbol Tables and Resources.
- Export function to convert all data, including job network graphics, to HTML.
- During the installation procedure, files with the extension \*.eor are associated with the Entire Operations Viewer executable. This means the Entire Operations Viewer is started automatically when you double-click on the file. When downloading Entire Operations files, you should therefore save them with this extension.

## Installation

- System Prerequisites
- Installation Procedure

### System Prerequisites

#### On the Mainframe:

- Recommended: Entire Connection 2.1.1 (for downloading data from master database) and Entire Operations 3.1.1.
- Assignment of the NATURAL Workfile 7 to the PC.

#### On the PC:

- One of the following Windows platforms: Windows 95, Windows 98, Windows NT4 or above.
- Intel 80386 compatible PC. At least 8 MB main memory. A display with a resolution of 800x600 pixels minimum and 256 colors are recommended.
- The language used by Entire Operations Viewer depends on the setting of the system language. German and English are supported.

- A Web Browser or another tool for viewing and printing HTML 3.0.

## Installation Procedure

### To install Entire Operations Viewer

- Run the **setup.exe** program from the installation disk or CD-ROM.

By default, Entire Operations Viewer is installed in the subdirectory

Program Files\Software AG\Entire Operations Viewer
--

During the installation process, you will be asked to enter your name, the name of the company you work for and your registration number.

If you have a non-English version of Windows, please note that the Program Files directory has a different language-specific name.