

Network

This section covers the following topics:

- Network Maintenance
- Network Retrieval

Network Maintenance

The Network Maintenance Menu is called with the command `MAINTAIN NETWORK`.

Overview of Functions and Commands

Function	Code	Command
Add a network	A	ADD NETWORK
Copy network	C	COPY NETWORK
Modify network	M	MODIFY NETWORK
Rename network	N	RENAME NETWORK
Purge network	P	PURGE NETWORK
Display network	D	see Retrieval
Link children	L	LINK NETWORK <active-association-type>
Edit owners of a network	O	EDIT NETWORK OWNER
Select network from a list	S	see Retrieval
Edit description	W	EDIT NETWORK DESCRIPTION

Parameters

Keyword	Field	Position
ID	Network ID	1
<>	Copy ID	2

Network-specific Maintenance Commands

Network objects are processed using Standard Maintenance Commands.

Network Retrieval

The Network Retrieval Menu is called with the command `RETRIEVE NETWORK`.

Overview of Functions and Commands

Retrieval Type	Code	Default Output Mode	Command
Networks	D	D	DISPLAY NETWORK
		L	LIST NETWORK
		S	SELECT NETWORK
		D	SHOW NETWORK
Execute retrieval models	E	T	EXECMODEL NETWORK
Dummy/Placeholder network	C	L	DUMMY NETWORK <passive-association-type>
Network with parents	B	D	PARENTS NETWORK <passive-association-type>
Network with no parent	O	L	FREE NETWORK ANY ALL <passive-association-type>
Network with children	T	D	CHILDREN NETWORK <active-association-type>
Network with no child	U	L	EMPTY NETWORK ANY ALL <active-association-type>
Vista numbers	N	L	LIST VISTATAB

Parameters

Keyword	Field	Position
ID	Network ID	1
RES	Restrictions	2
OUT	Output options	3
MODEL	Model	4
MODE	Output mode	5

Network-specific Retrieval Command

See Standard Retrieval Commands.

Command	Description
LIST VISTATAB	Displays information on the use of Vista numbers in list form. For more information see Network in the Predefined Object Types in Predict documentation.