

# Natural Nucleus Error Messages

## NAT1451-NAT1500

**NAT1500: Open for :1: file :2: failed :3:.**

|       |  |
|-------|--|
| Text  | Open for ... file ... failed ....  |
| Expl. | Possible reasons: <ul style="list-style-type: none"><li>- Complete: Workfiles: Insufficient space for SD-files.</li><li>Printers : Message indicates the PSOPEN error.</li><li>- MVS: Insufficient or incorrect DCB information. Please check for operating system messages in the job log.</li><li>- VSE: Dataset not allocated in job control.</li><li>- BS2: see the DMS error code for information. One cause for example, may be code DD33 - file does not exist.</li><li>- UNIX/PC: Read/write privileges for the directory where the work file is located may be incorrect. Or the specified path for the work file may be incorrect.</li></ul> |
| Actn. | Contact your Natural administrator.  |