

Console Messages XCO0009I to XCO0019E

Message	Explanation	Action
XCO0009I X-COM node is initialized.	X-COM has initialized the target and is ready for work.	No action required.
XCO0010W Wrong ECB found.	The type of returned event indicator is not valid and will be ignored. X-COM nucleus continues to wait for requests.	Please contact Software AG.
XCO0011E X-COM data error.	The routine to check X-COM data has detected an inconsistency. X-COM nucleus terminates abnormally.	Please contact Software AG.
XCO0012E USER RET (R15) error.	One of the routines called by X-COM nucleus has returned an error. X-COM nucleus terminates abnormally.	Please contact Software AG.
XCO0013E Delete ECB error.	An ECB cannot be removed from the wait list. X-COM nucleus terminates abnormally.	Please contact Software AG.
XCO0014E No ANSWER entry point.	The entry point for the reply handler could not be found. X-COM nucleus cannot process any user replies and terminates abnormally.	Please contact Software AG.
XCO0015E APPL ECB already deleted.	The X-COM nucleus was posted to send the reply to the user but could find the related X-COM data. X-COM nucleus ignores the post and continues to wait for requests.	No action required.
XCO0016I Operator typed in: :1:.	Message confirming operator input.	No action required.
XCO0019E X-COM parm list wrong.	The request or reply handler has returned inconsistent data. X-COM nucleus terminates abnormally.	Please contact Software AG.