

## Console Messages XCO0009I to XCO0019E

Message	Explanation	Action
<b>XCO0009I</b> X-COM node is initialized.	X-COM has initialized the target and is ready for work.	No action required.
<b>XCO0010W</b> Wrong ECB found.	The type of returned event indicator is not valid and will be ignored. X-COM nucleus continues to wait for requests.	Please contact Software AG.
<b>XCO0011E</b> X-COM data error.	The routine to check X-COM data has detected an inconsistency. X-COM nucleus terminates abnormally.	Please contact Software AG.
<b>XCO0012E</b> USER RET (R15) error.	One of the routines called by X-COM nucleus has returned an error. X-COM nucleus terminates abnormally.	Please contact Software AG.
<b>XCO0013E</b> Delete ECB error.	An ECB cannot be removed from the wait list. X-COM nucleus terminates abnormally.	Please contact Software AG.
<b>XCO0014E</b> No ANSWER entry point.	The entry point for the reply handler could not be found. X-COM nucleus cannot process any user replies and terminates abnormally.	Please contact Software AG.
<b>XCO0015E</b> APPL ECB throw away.	The X-COM nucleus was posted to send the reply to the user but could find the related X-COM data. X-COM nucleus ignores the post and continues to wait for requests.	No action required.
<b>XCO0016I</b> Operator typed in: :1:.	Message confirming operator input.	No action required.
<b>XCO0019E</b> X-COM parm list wrong.	The request or reply handler has returned inconsistent data. X-COM nucleus terminates abnormally.	Please contact Software AG.