

Automated Cartridge System Library Software

Messages

Version 6.1.1

313495902

The information in this document is confidential and proprietary to Storage Technology Corporation and may be used only under the terms of the product license or nondisclosure agreement. The information in this document, including any associated software program, may not be disclosed, disseminated, or distributed in any manner without the written consent of Storage Technology Corporation.

Limitation on Warranties and Liability

This document neither extends nor creates warranties of any nature, expressed or implied.

Storage Technology Corporation cannot accept any responsibility for your use of the information in this document or for your use of any associated software program. Storage Technology Corporation assumes no responsibility for any data corruption or erasure as a result of the use of the information in this document, or the use of software programs. You should be careful to ensure that your use of the information complies with all applicable laws, rules, and regulations of the jurisdictions with respect to which the information is used.

Warning: No part or portion of this document may be reproduced in any manner or in any form without the written permission of Storage Technology Corporation.

Restricted Rights

Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c) (1) (ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227–7013 or subparagraphs (c) (1) and (2) of the Commercial Computer Software — Restricted Rights at 48 CFR 52.227–19, as applicable.

Trademarks

The following terms are either trademarks or registered trademarks of Storage Technology Corporation: Storage Tek ${}^\circledR$

Nearline®

IBM® is a registered trademark of International Business Machines Corporation.

Other product names mentioned in this manual may be trademarks. They are used for identification purposes only.

ACSLS 6.1.1 Messages, 12th Edition December, 2002

EC 128637 Part Number 313495902

This edition applies to the Messages document of Version 6.1.1 of Automated Cartridge System Library Software. Information contained in this publication is subject to change. Comments concerning the contents of this manual should be directed to:

Storage Technology Corporation
Manager, Software Information Development, MS 5209
One StorageTek Drive
Louisville, Colorado 80028–5209

OR

OK

E-mail us at: sid@stortek.com

[©] Copyright Storage Technology Corporation 2002. All Rights Reserved.

Document Effectivity

EC Number	Date	Doc Kit Number	Edition Type	Effectivity
123273	May 2001		Ninth Edition	This document applies to Automated Cartridge System Library Software (ACSLS), Version 6.0
123359	August 2001		Tenth Edition	This document applies to Automated Cartridge System Library Software (ACSLS), Version 6.0.1
128533	June 2002		11th Edition	This document applies to Automated Cartridge System Library Software (ACSLS), Version 6.1.
128637	December 2002		12th Edition	This document applies to Automated Cartridge System Library Software (ACSLS), Version 6.1.1.

Contents

Document Effectivity	iii
About this Book	vii
Audience	viii
Reader's Comments	viii
About the Software	ix
How this Guide is Organized	X
Conventions for Reader Usability	X
Typographic	X
Enter Command	xi
Technical Support	хi
Related Documentation	xii
ACSLS 6.1.1 Documentation	xii
ACSLS Information on the StorageTek CRC	xiii
ACS Hardware Information on the StorageTek CRC	
Event Log Messages	1
Format for Messages	
Gathering Diagnostic Information for ACSLS Issues	
Messages	
1377 Messages	
Glossary	225

About this Book

The messages listed in this book are ACSLS Event Log messages that are likely to appear most frequently in the Log.

Some of the messages in this book also appear in the Display area of the command processor as unsolicited messages. Other locations for ACSLS messages include the following:

- The command area of the command processor
- UNIX command tool window
- The files in the log directory (\$LOG_PATH)

Audience

This book was written for system administrators and library operators who perform library commands and other ACSLS functions.

Reader's Comments

We'd like to know what you think about this book. If you prefer, you can e-mail your comments to Software Information Development directly. Our Internet address is:

sid@stortek.com

Be sure to include the document title and number with your comments.

About the Software

This book supports ACSLS 6.1.1.

Note: The StorageTek Customer Resource Center (CRC) on the World Wide Web lets you download ACSLS PTFs and software support for product enhancements such as new drive or library types.

To access ACSLS PTFs and software support for product enhancements:

1. Using an Internet browser such as Netscape, go to the StorageTek CRC. The URL is:

http://www.support.storagetek.com/

- 2. Select the Request a Login and Password link.
- 3. Fill in the information requested in the form.

You should receive your account ID and password within two days.

4. After you are logged in, select

Product Information

Current Products

Select a Product Family: Software

Select ACSLS

(You may want to "View All" to see all the maintenance or documentation.)

How this Guide is Organized

This book contains the following information on each message:

- The message text
- An explanation of the message
- A description of any variables appearing in the message
- The action required to respond to the message

Conventions for Reader Usability

Conventions are used to shorten and clarify explanations and examples within this book.

Typographic

The following typographical conventions are used in this book:

- Bold is used to introduce new or unfamiliar terminology, or it's used in steps to indicate either an action or a decision the user has to make.
- Letter Gothic is used to indicate filenames, command names, and literal output by the computer.
- Letter Gothic Bold is used to indicate literal input to the computer by you.
- Letter Gothic Italic is used to indicate that you must substitute the actual value for a command parameter. In the following example, you would substitute your name for the "username" parameter.

Logon username

A bar (|) is used to separate alternative parameter values.
 In the example shown below either username or systemname must be entered.

Logon *username* | *systemname*

 Brackets [] are used to indicate that a command parameter is optional.

Enter Command

The instruction to "press the [ENTER] key" is omitted from most examples, definitions, and explanations in this book.

For example, if the instructions asked you to "enter" **Logon pat**, you would type in **Logon pat** *and* press [ENTER].

However, if the instructions asked you to "type" **Logon pat**, you would type in **Logon pat** and you would *not* press [ENTER].

Technical Support

Refer to the *Requesting Help from Software Support*, automatically shipped in hard copy only with the ACSLS 6.1.1 program package, for information about contacting StorageTek for technical support and for requesting changes to software products.

Related Documentation

ACSLS 6.1.1 Documentation

The following publications provide more information about ACSLS 6.1.1:

- The ACSLS 6.1.1 Information CD–ROM, part number: 313495503, which is automatically shipped with the 6.1.1 program package and provides PDF format of all the ACSLS 6.1.1 publications.
- ACSLS Product Information, part number: 313496102, also provided in PDF format on the ACSLS 6.1.1 Information CD-ROM and on the StorageTek Customer Resource Center (CRC). It is also shipped in hardcopy.
- ACSLS Installation, Configuration, and Administration Guide, part number: 313495803, in PDF format on the ACSLS 6.1.1 Information CD–ROM and on the StorageTek Customer Resource Center (CRC); hardcopy of the guide is also shipped with the program package.
- *ACSLS Quick Reference*, part number: 313496002, which is shipped with the 6.1.1 program package.
- ACSLS 6.1.1 *Read Me First*, part number: 313496202, which is shipped with the 6.1.1 program package.

ACSLS Information on the StorageTek CRC

In addition to the PDF collections on the ACSLS 6.1.1 Information CD–ROM, the StorageTek CRC provides PDF collections for ACSLS 6.1.1. Use the following procedure to access this collection on the StorageTek CRC.

To access ACSLS PDF collections on the StorageTek CRC:

1. Using an Internet browser, go to the StorageTek CRC. The URL is:

http://www.support.storagetek.com/

- 2. Select the Request a Login and Password link.
- 3. Fill in the information requested in the form. You should receive your account ID and password within two days.
- 4. When you receive your account information, go back to the CRC and select the Login link.

When prompted, fill in your User ID and password.

5. After you are logged in, select **Product Information Current Products** Select a Product Family: Software Select ACSLS

> (You may want to "View All" to see all the maintenance or documentation.)

ACS Hardware Information on the StorageTek CRC

The StorageTek CRC provides PDF file format of many of StorageTek's ACS hardware publications. Use the following procedure to access these publications on the StorageTek CRC.

To access StorageTek ACS hardware documentation on the StorageTek CRC:

1. Using an Internet browser such as Netscape, go to the StorageTek CRC. The URL is:

http://www.support.storagetek.com/

- 2. Select the Request a Login and Password link.
- 3. Fill in the information requested in the form. You should receive your account ID and password within two days.
- 4. When you receive your account information, go back to the CRC and select the login link.

When prompted, fill in your User ID and password.

5. After you are logged in, select **Product Information Current Products**

Select a Product Family: Hardware

Select the hardware product documentation you want.

Event Log Messages

This book lists Event Log messages in numeric order. The message number is the number that appears at the beginning of the second line of the message you see in the Event Log. In this book, the message number is followed by the message text, which is the last line you see in the Event Log message. For a description of the complete message that you see in the Event Log, go to "Format for Messages" on page 2.

Each message description in this book contains the following information:

- The message number and message text
- An explanation of the message
- A description of any variables appearing in the message
- Any action necessary to respond to the message

Format for Messages

All Event Log entries have a consistent format. Each entry contains a one-line prefix followed by module information and two or more lines of message text.

Event Log Format

The generic format for all entries is:

mm-dd-yy hh:mm:ss component_name[nn]:
message_number classification mod_id mod_ver mod_line
function: One or more lines of message text...

A specific example of an Event Log entry is:

Example:

12-06-95 10:58:32 storage server[0]: 351 N ss_main.c 5.24 562 ss_main:01 Initiation completed

The first line of the message contains three elements:

- *mm-dd-yy hh:mm:ss* are the date and time of entry.
- component_name is an abbreviation for the originating library server component, for example, ACSLM, ACSSA, CSI, storage server, etc.
- [nn] is the request ID enclosed in square brackets. This ID is generated by the ACSLM when it receives a valid request. You can enter a query request command to check the status of the request specified by the request ID.

The second and subsequent lines contain the following information:

- message number is the number of the message.
- *classification* is a one-letter classification of the message. These classifications are as follows:
 - N not classified
 - \circ **I** information only
 - \circ **E** error
 - \circ W warning
- mod_id, mod_ver, and mod_line indicate respectively the file name of the ACSLS module that generated the message, the module version, and the module line number. These identifiers are included to help StorageTek support personnel isolate the cause of the problem. They are not intended to be used by system administrators or library users.
- function is the component function that generated the message. Error messages (E) generally include function. Informational messages (I) generally omit function. (See line three of the generic format for all entries, shown on the preceding page).
- *message text* is the message itself. Note that the message may take up one or more lines of text.

Gathering Diagnostic Information for ACSLS Issues

When the action required in response to an error message is to call StorageTek Software Support you will need to provide diagnostic information so that StorageTek Software Support can assist you to resolve the problem. The minimum you will need to provide is the Event Log containing the error message. The following describes additional information that may be useful for diagnosing problems.

Requesting Help from Software Support

For more information about contacting StorateTek Software Support, download *Requesting Help from Software Support*. Go to the StorageTek website (www.support.StorageTek.com) using your usual login and password. Click on Customer Resource Center and choose "Product Support" from the "User Services" menu. Click on "on–line guide" under "Special Notes" in the Software row of the Technical Support table.

Gathering ACSLS Diagnostic Information

Use the data gathering tool to collect complete ACSLS diagnostic information for StorateTek Software Support.

- Login as root
- Change to the diag/bin/ directory
 cd \$ACS_HOME/diag/bin
- Gather diagnostic information
 - ./get_data.sh
- This creates a file containing a collection of diagnostic informtion: \$ACS HOME/log/output.tar.Z
- After you contact StorageTek Software Support about your issue, please send them the \$ACS_HOME/log/output.tar.Z file.

Gathering Additional Diagnostic Information Requested by ACSLS Support

ACSLS Support may request that a customer gather additional diagnostic information, including traces of communications between ACSLS and both clients and tape libraries.

Messages

O I message text

Explanation: An error occurred and is described by the variable *message text*.

Variable: *message text* describes the error.

Action Required: Resolve the error condition; if you need assistance, gather the information required, described above, and collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support. This error message may indicate a lost volume condition; for more information, see "Recovering Errant (Lost) Volumes" in "Appendix B: Troubleshooting" of the ACSLS Installation, Configuration, and Administration Guide.

1 N unexpected status = status

Explanation: An ACSLS function received an unexpected status code from another ACSLS function.

Variable: *status* is the code being passed between functions.

Action Required: If the error recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

4 N LSM lsm id: Access door closed

Explanation: The LMU has passed a message to ACSLS which indicates that the LSM access door was just closed.

Variable: *lsm id* is the LSM whose access door is closed.

Action Required: None; this message is informational only.

5 N LSM lsm id: Access door opened

Explanation: The LMU has passed a message to ACSLS that indicates that the LSM access door was just opened.

Variable: *lsm id* is the LSM whose access door is open.

Action Required: None; this message is informational only.

6 N ACS Identifier acs id Invalid

Explanation: The ACS identifier or variable is in the wrong format or has an invalid value.

Variable: *acs id* is the ACS identifier that is invalid.

Action Required: Enter the correct format (see "Component Types and Identifiers" in the "General Command Syntax" section of the "Command Reference" Chapter of the *ACSLS Installation, Configuration, and Administration Guide*) for the correct format for the ACS identifier.

9 N LSM Identifier *lsm_id* Invalid

Explanation: The LSM identifier or variable is in the wrong format or has an invalid value.

Variable: *lsm id* is the LSM identifier that is invalid.

Action Required: Enter the correct format (see "Component Types and Identifiers" in the "General Command Syntax" section of the "Command Reference" Chapter of the *ACSLS Installation, Configuration, and Administration Guide*) and/or the correct identifier value.

20 N Invalid exit status status returned from PID process-id

Explanation: The exit status returned from the process ID (PID) was not considered a valid exit status.

Variable:

- *status* is the exit status returned from the process ID.
- process-id is the process ID value.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

37 N LMU READY received for ACS Identifier acs id

Explanation: An LMU has been placed online.

Variable: *acs_id* is the identifier of the ACS to which the LMU is connected.

Action Required: None; this message is informational only.

38 N LSM NOT READY received for LSM Id lsm id.

Explanation: The LSM has been taken offline.

Variable: *lsm_id* is the identifier of the LSM that has gone

offline.

Action Required: None; this message is informational only.

40 N LSM READY received for LSM Identifier lsm id.

Explanation: The LSM has been placed online.

Variable: *lsm_id* is the identifier of the LSM that is online.

Action Required: None; this message is informational only.

 $\textbf{43 N} \hspace{0.1cm} \texttt{PORT} \hspace{0.1cm} \texttt{OFFLINE} \hspace{0.1cm} \texttt{received} \hspace{0.1cm} \texttt{for} \hspace{0.1cm} \texttt{PORT} \hspace{0.1cm} \texttt{Id} \hspace{0.1cm} port_id$

Explanation: A port between the server system and the LMU has been taken offline.

Variable: *port_id* is the identifier of the port that has gone offline.

Action Required: None; this message is informational only.

53 N cell *cell id* - Reserved too long by another process

Explanation: A cell record in the database has been reserved by another process, and the audit is unable to access it after the appropriate number of retries and timeouts. The audit continues with the next cell. This error indicates that the system is under a heavy load.

Variable: *cell id* is the identifier of the cell record.

Action Required:

- 1. Issue a query request all to see if there are any requests active for the cell. See the "Command Reference" Chapter of the *ACSLS Installation, Configuration, and Administration Guide* for information on issuing commands.
- 2. If there are no requests active, issue an audit request for the subpanel containing the designated cell. See the "Command Reference" Chapter of the ACSLS Installation, Configuration, and Administration Guide for information on issuing commands.
- 3. If the problem persists, a software failure has occurred and the library server must be restarted. See the "Command Reference" Chapter of the *ACSLS Installation*, *Configuration*, *and Administration Guide* for information on issuing commands.

54 N Cell *cell id* - Missing cell detected

Explanation: The LSM robot is unable to locate a storage cell in the LSM. Possible causes are that the L-shaped target has been wiped off the cell or the cell carrier has detached from the LSM wall. This is a library configuration error and causes the library server to terminate.

Variable: *cell id* is the location of the missing cell.

Action Required: The audit should be rerun after the error has been corrected and the library server has been reinitiated.

55 N Panel panel id - Audit of panel completed

Explanation: For ACS, LSM, or server audits, this message is written to the Event Log for each panel that has been audited.

Variable: *panel_id* is the location of the panel that has been audited.

Action Required: None; this message is informational only.

65 N Cartridge vol id found at location cell id

Explanation: A tape cartridge **not** listed in the database has been found in the ACS. The cartridge is added to the database.

Variable:

- The *vol id* is the external label of the tape cartridge.
- The *cell_id* is the storage cell location where the cartridge was found.

Action Required: None; this message is informational only.

66 N Cartridge vol id, new location cell id

Explanation: A tape cartridge is not in the location defined by the database. The cartridge is not moved in the ACS; instead, the database is updated to reflect the new storage location.

Variable: The *vol_id* is the external label of the tape cartridge. The *cell_id* is the assigned storage cell location of the cartridge.

Action Required: None. This message is informational only.

67 N Cartridge vol id not found

Explanation: A tape cartridge listed in the database was not found in the ACS. The cartridge was removed from the database.

Variable: The *vol_id* is the external label of the tape cartridge. **Action Required:** None; this message is informational only.

75 N Unexpected Automatic Enter Request received: discarded.

Explanation: The CAP closed at a time when the request queue was empty. There was no matching request to which the CAP closure should be associated. The CAP closure is ignored.

Action Required: Observe related event log messages for clues to the possible cause of this condition.

81 N ACS acs id configuration failed to verify

Explanation: The ACS configuration in the library server database does not match the configuration defined in the LMU. Recovery processing terminates.

Variable: acs id is the unique identifier of the ACS.

Action Required: After recovery processing terminates, rerun the library server acsss_config program to redefine the library configuration in the database (see the *Installation and Configuration Guide* for your platform).

83 N Drive drive id: Configuration failed to verify

Explanation: The recovery process was unable to successfully verify the drive configuration in the database against the configuration defined in the LMU. This condition may be because the LSM is offline or because there is an actual configuration mismatch.

Variable: *drive_id* is the unique identifier of the drive.

Action Required: Issue a query <code>lsm</code> request to display the state of the LSM. If it is online, you must run the <code>acsss_config</code> program to redefine the configuration in the library server database:

- 1. Check the drive for any problems.
- 2. If there are drive problems, fix them.
- 3. Vary the drive and the LSM online.
- 4. If the problem persists, or if the drive is new or has been removed, run acsss_config. See "Chapter 6: Configuring your Library Hardware" in the *ACSLS Installation*, *Configuration, and Administration Guide* for more information on procedures for reconfiguring ACSLS.

85 N LSM lsm id: configuration failed to verify

Explanation: The LSM configuration in the database does not match the configuration defined in the LMU. Recovery processing terminates. This message will be followed by a Server system recovery failed message.

Variable: *lsm_id* is the LSM whose configuration does not match that defined in the LMU.

Action Required: Check previous Event Log entries for additional information about the failure. Follow the suggested action for the associated error message(s).

87 N ACS acs id: No ports online: marked offline

Explanation: The server system is not able to communicate with any ports for the specified ACS. Recovery will continue, but the ACS and its LSMs are marked as offline in the database.

Variable: *acs id* is the ACS that was updated.

Action Required: When recovery completes, do the following:

- 1. Vary the port online.
- 2. Does this correct the problem?

YES	Vary the ACS online. Action completed.	
NO	Follow the remaining steps in this procedure.	

- 3. Find and fix any problem with the port. Among other conditions, check these:
 - o The LMU is down.
 - A cable is missing or there is a bad connection.
 - The port is bad.
- 4. Vary the port online.
- 5. Vary the associated ACS(s) online.

Note: If you have more than one ACS, repeat the steps above for each additional ACS.

88 N No server ports online

Explanation: The server system is not able to communicate with any ACS. Recovery continues, but all ACSs and their LSMs are marked as offline.

Action Required: To vary an ACS online, at least one communications port to the ACS must be online. When recovery completes, do the following:

- 1. Issue vary online requests to the appropriate port(s).
- 2. Vary all associated ACSs online.

89 N Port port id: Failed to go online: marked offline

Explanation: The server system can not communicate with a port to an ACS. The port is marked offline in the database.

Variable: *port_id* is the port that failed to go online.

Action Required: Check the communications line between the server system and the LMU. If the line is intact, issue a vary online request for the designated port.

94 N Cell cell id: Corrected cell status to status

Explanation: The status of a cell record was updated based on ACSLS processing.

Variable:

- *cell_id* is the specific cell which was updated.
- *status* indicates the new status of the cell.

Action Required: None. This is a notification only.

95 N Drive drive id: Corrected drive status to status

Explanation: The status of a drive record was updated based on ACSLS processing.

Variable:

- *drive_id* is the specific drive which was updated.
- *status* indicates the new status of the drive.

Action Required: None. This is a notification only.

96 N Volume vol id: Corrected volume status to status

Explanation: The status of a volume record was updated based on ACSLS processing.

Variable:

- *vol id* is the specific volume which was updated.
- *status* indicates the new status of the volume.

Action Required: None. This is a notification only.

100 N LSM *lsm_id:* Hardware failed to vary offline/online: marked offline

Explanation: A request to vary an LSM offline was processed to completion, but the LSM failed to vary offline.

Variable: *lsm id* is the LSM in the request.

Action Required: Run the library diagnostics to help isolate the cause of the problem (see the appropriate hardware maintenance manual for instructions). If more help is needed, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

Explanation: ACSLS found this volume in the playground/in–transit cell or in a PCP cell while recovering an LSM. It attempted to recover the volume by moving it to a new home cell in this LSM. However, the volume could not be recovered, as the LSM was full, so the volume was marked deleted in the database.

Variable:

- *lsm id* identifies the LSM being recovered.
- *vol id* identifies the deleted volume.

Action Required:

- 1. Eject a volume from the LSM.
- 2. Vary the LSM offline and back online to recover the volume.

105 N component component id: Overridden by another vary request

Explanation: The specified component was not varied to the specified state because the request was overridden by another vary request.

Variable:

- *component* is the library component (for example, ACS).
- *component_id* is the identifier of the library component.

Action Required: None; this message is informational only. If desired, resubmit the vary request.

113 N File file: operation failed on \"%s\" (errno=error no)

Explanation: An operation performed on an Event Log file failed.

Variable:

- file is the file on which the operation failed.
- *operation* is the operation that failed.
- *error_no* is the system error number associated with this file operation problem.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

115 N Volume *vol_id*: Corrected volume type from *media_type1* to *media_type2* cartridge

Explanation: An ACSLS audit detected a volume with an incorrect media type. The audit updated the ACSLS database with the correct volume media type.

Variable:

- *vol id* is the volume ID.
- *media type1* is the incorrect volume media type.
- media type2 is the corrected volume media type.

Action Required: None; this message is informational only.

122 E surr_main (PID ####): Creating socket SURROGATE failed on "#####"

Explanation: The Surrogate main routine tried to create a socket (using the socket() system call) to listen for requests from the Library Management Gateway. Each Surrogate process that is running has its own unique socket. The system's response is to use the acsss_daemon to abnormally terminate the IPC Surrogate and automatically restart ACSLS (up to 10 times).

Variable: ##### is the process ID of the Surrogate trying to create a socket.

Action Required:

- Look for associated errors that may indicate why the socket() call failed.
- Kill the ACSLS system using the kill.acsls command, then kill any additional "zombie" ACSLS processes (using a ps | grep acs)
- Then restart ACSLS. It may be necessary to reboot the ACSLS host to release any hung sockets.
- If the problem persists, check to see whether UNIX system limits have been exceeded on sockets, file descriptors, or other network resources.
- If the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

125 N Volume *vol_id*: Locked volume deleted, lock was *lock_id*

Explanation: A volume with a non-zero lock identifier was deleted.

Variable:

- *vol id* is the volume identification.
- *lock id* is the identifier of the lock.

Action Required: None; this message is informational only.

126 N Timed out waiting for message

Explanation: A process passed an internal request to another process. The latter did not respond within the designated timeout period.

Action Required: Observe related event log messages for clues to the possible cause of this condition.

130 E surr_main (PID #####): Environment variable SURROGATE_QUEUE_AGE is not defined or has a null value: exiting

Explanation: The Surrogate main routine was unable to get the SURROGATE_QUEUE_AGE dynamic environment variable or the variable is not correctly set. IPC Surrogate terminates.

Variable: ##### is the process ID of the Surrogate issuing the error.

Action Required: Define the SURROGATE_QUEUE_AGE variable with the acsss_config program.

130 E surr_main (PID #####): Environment variable SURROGATE_TIMEOUT is not defined or has a null value: exiting

Explanation: The Surrogate main routine was unable to get the SURROGATE_TIMEOUT dynamic environment variable or the variable is not correctly set. IPC Surrogate terminates.

Variable: ##### is the process ID of the Surrogate issuing the error.

Action Required: Define the SURROGATE_TIMEOUT variable with the acsss_config program.

130 E surr_main (PID #####): Environment variable SURROGATE_PORT is not defined or has a null value: exiting

Explanation: The Surrogate main routine was unable to get the SURROGATE_PORT dynamic environment variable or the variable is not correctly set. IPC Surrogate terminates.

Variable: ##### is the process ID of the Surrogate issuing the error.

Action Required: Define the SURROGATE_PORT variable with the acsss_config program.

135 N Unexpected ACSLH catalog status status detected

Explanation: After a catalog request was issued by an ACSLS component, a response was received but contained a status code which was not expected by the requesting component.

Variable: *status* is the specific status code.

Action Required: None. Refer to the event log for additional information.

141 N Unexpected message detected, IPC identifier is ipc id

Explanation: An orphaned response is returned from one process to another that does not match any outstanding request.

Action Required: Observe related event log messages for clues to the possible cause of this condition.

146 N Unexpected status status detected

Explanation: An ACSLS function received an unexpected status code from another ACSLS function.

Variable: status is the code being passed between functions.

Action Required: If the message recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

148 N Volume vol id Unknown media type detected

Explanation: While performing Cartridge Recovery, a cartridge with a readable label was encountered for which no volume record was recorded in the database. In the process of adding a volume record, an attempt was made to determine volume type based on media type. That attempt failed because the media type was unknown.

Variable: *vol_id* is the specific volume identifier of the cartridge.

Action Required: None.

149 N Removing file file: failed on cause of failure

Explanation: An operation performed on an Event Log file failed.

Variable:

- file is the name of the event log file.
- cause of failure is the cause of the operation's failure.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

152 N Unsupported version version packet detected: discarded

Explanation: The ACSLS CSI detected an unsupported packet version on a request.

Variable: version is the unsupported packet version.

Action Required: Either update the client application to use a supported packet version or, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

153 N Volume *vol_id*: Found in *cell/CAP/drive/recovery cell id/CAP id/drive id/cell* added

Explanation: This message is issued when a misplaced tape is found in the library by vary or CAP processing.

Variable:

- *vol id* is the identifier of the volume that was found.
- *cell/CAP/drive/recovery* is the location type where the volume was found.
- cell_id/CAP_id/drive_id/cell is the identifier of the location where the volume was found. Note that, in the case of a volume being found in the playground area (recovery), only the word cell, not the cell_id, is output.

154 W Misplaced cartridge detected; volume *vol_id* cannot be recovered and is deleted

Explanation: ACSLS found this volume in the playground/in–transit cell or in a PCP cell while recovering an LSM. It attempted to recover the volume by moving it to a new home cell in this LSM. However, the move failed because the destination cell contained a cartridge. The volume has not been recovered and is marked deleted in the database.

Variable: *vol id* identifies the deleted volume.

Action Required:

- 1. Check to make sure that the problem is not a single misplaced cartridge.
- 2. If it is not, audit the LSM to update the ACSLS database to match the actual contents of the library.
- 3. Vary the LSM offline and back offline to recover the volume.

155 N Volume vol id: New home location is cell cell id

Explanation: When checking a storage cell, Cartridge Recovery encountered a cartridge that appeared to be misplaced. The recorded home cell for that cartridge was checked and found to be either empty or full with some other cartridge.

Variable:

- *vol id* is the specific volume identifier of the cartridge.
- *cell id* is the cell in which the cartridge was found.

Action Required: None. The volume record for this cartridge is updated to reflect the new home cell location.

187 N audit started

Explanation: Audit processing has begun.

240 E Cartridge Recovery () unexpected status = STATUS_LIBRARY_NOT_AVAILABLE

Explanation: When checking storage cells, Cartridge Recovery was unable to check an LSM that was idle.

Action Required: None; this message is informational only.

241 N audit completed not all cartridges were ejected, messages lost status = *audit completion status*

Explanation: A spawned audit process has sent an incomplete or unintelligible message to the parent audit process. As a result, some errant cartridges may not be ejected.

Variable: *audit_completion_status* is the status of the audit upon its completion.

Action Required: To respond to this message, do the following:

- 1. Check previous Event Log entries to determine the reason for the lost message(s).
- 2. If the *audit_completion_status* is Audit cancelled or Audit failed, the audit should be rerun.
- 3. If the audit continues to fail, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

243 N audit completed

Explanation: Audit processing has completed successfully.

244 N audit cancelled not all cartridges were ejected, messages lost status = audit_completion_status

Explanation: A spawned audit process has sent an incomplete or unintelligible message to the parent audit process. As a result, some errant cartridges may not be ejected.

Variable: *audit_completion_status* is the status of the audit upon its completion.

Action Required: To respond to this message, do the following:

- 1. Check previous Event Log entries to determine the reason for the lost message(s).
- 2. If the *audit_completion_status* is Audit cancelled or Audit failed, the audit should be rerun.
- 3. If the audit continues to fail, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.
- 4. If the *audit_completion_status* is Audit complete, no action is required, as the audit has completed successfully.

245 N audit cancelled

Explanation: Audit processing has been cancelled. The database may have discrepancies or errant cartridges may not have been ejected.

246 N audit failed not all cartridges were ejected, messages loststatus = audit completion status

Explanation: A spawned audit process has sent an incomplete or unintelligible message to the parent audit process. As a result, some errant cartridges may not be ejected.

Variable: *audit_completion_status* is the status returned by the audit.

Action Required: To respond to this message, do the following:

- 1. Check previous Event Log entries to determine the reason for the lost message(s).
- 2. If the *audit_completion_status* is Audit cancelled or Audit failed, the audit should be rerun.
- 3. If the audit continues to fail, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.
- 4. If the *audit_completion_status* is Audit complete, no action is required, as the audit has completed successfully.

247 N audit failed

Explanation: Audit processing has terminated due to some error condition. The description of the error is displayed in the Command Area. The database may have discrepancies or errant cartridges may not have been ejected.

Action Required: Check previous Event Log entries to determine the cause of the failure. Follow the suggested action for the associated message(s). Once this is done, rerun the audit.

252 N audit failed not all cartridges were ejected, status = status

Explanation: An ACSLS audit was interrupted (for example, by an idle force command or a hardware failure).

Variable: *status* describes the event that interrupted the audit.

Action Required: Resubmit the audit.

317 N Lock request size incorrect .Req = *string1*, Exp = *number1*, Rec = *number2*

Explanation: The size of the lock request submitted does not match the expected byte count.

Variable:

- *string1* is the current type of lock request.
- *number1* is the expected byte count of the current lock request.
- *number2* is the actual byte count of the current lock request.

Action Required: Re-submit the lock request with the correct information in the request.

347 N Initiation started, acsss version

Explanation: Library server initiation has begun.

Variable: acsss version is the ACSLS version number.

Action Required: None; this message is informational only.

351 N Initiation completed (library server)

Explanation: Product initiation completed successfully.

352 N wait() return invalid PID PID

Explanation: The *PID* returned by wait is not the expected PID.

Variable: *PID* is the process ID returned by wait().

Action Required: Restart ACSLS, if needed. If restarting ACSLS fails after three tries, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

354 N exit status ($status_code$), status, received from process name

Explanation: The library server daemon has received an unexpected exit status from a library server process.

Variable:

- *status_code* is the library server status code that was generated as a result of the exit.
- *status* is the numeric exit status from the process.
- process_name is the library server process.

Action Required: If this error occurs when not shutting down ACSLS or issuing an idle force command, check the following conditions:

Condition	Action
Processing continues, no more errors.	No action. Message informational only.
Processing continues but the same error continues over a period of days, weeks, or months.	Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.
Processing does not continue.	Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

355 N signal (signal num) terminated process name

Explanation: An ACSLS process died from the specified signal. ACSLS will either restart the process or terminate depending on which process terminated. This message is informational only if it was received when shutting down ACSLS.

Variable:

- *signal_num* is the signal number received that terminated the process.
- process_name is the library server process that terminated.

Action Required: Restart ACSLS, if needed. See "Restarting ACSLS" in "Chapter 1: Overview" of the *ACSLS Installation*, *Configuration, and Administration Guide* for procedures on restarting ACSLS. If restarting ACSLS fails after three tries, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

356 N Termination invoked, termination status

Explanation: Library server termination has begun.

Variable: *termination_status* is the library server status code which indicates the reason for the termination.

Action Required: Follow the suggested action for the appropriate *termination status*:

If termination_status is STATUS_TERMINATED, there is no action, as this indicates a manually invoked termination of the software by the acsss user.

If *termination_status* is STATUS_DATABASE_ERROR, use the following procedure:

1. Attempt to restart the library server software with the rc.acsss command file.

You may be prompted for the acsss user password. If you are acsss or root, you will not be prompted.

2. Did the library server restart successfully?

YES	Go to Step 3.
NO	Go to Step 4.

- 3. Run the database recovery utility, rdb.acsss (as the acsss user).
 - a. rdb.acsss prompts you to enter a tape. Enter the most recent backup tape you have, since this utility writes over your existing database. (If you do not
 - have a current backup tape, enter [CTRL]]+C to quit out of this procedure.)
 - b. When rdb.acsss completes successfully, attempt to restart the library server software with the rc.acsss utility.
- 4. Perform an audit to reconcile the database with the physical contents of the library.

5. If none of the above steps are successful, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

If termination_status is STATUS_CONFIGURATION_ERROR, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support. Your support representative will adjust the LMU configuration to make it match the physical configuration of the library. Once this has been done, rerun the library server configuration program to redefine the library configuration in the database.

If termination_status is STATUS_RECOVERY_FAILED, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

357 N wait failed, ret = wait return code, errno= error no

Explanation: The UNIX system call wait() failed.

Variable:

- wait return code is the code returned by the wait.
- *error no* is the system error number.

Action Required: Restart ACSLS, if needed. If restarting ACSLS fails after three tries, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

361 N process name restarted, pid process id

Explanation: A library server process has been automatically restarted.

Variable:

- process_name is the library server process that was terminated.
- process id is the library server process identifier.

Action Required: If this message recurs over a period of days, weeks, or months, Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

368 N Unreadable Label cell id

Explanation: The robot was unable to decipher the external label of the volume.

Variable: *cell_id* is the storage cell location where the volume resides.

Action Required: Eject the volume and inspect the label. If you cannot determine which volume to eject, submit the following command:

sql.sh "select volid from volumetable where acs=v and lsm=w and panel=x and row=y and column=z."

where v, w, x, y, and z are the corresponding values for acs, lsm, panel, row, and column.

If this error occurs frequently with good labels, contact your StorageTek Customer Service Engineer (CSE) to inspect the robotic vision system.

371 N Destination location full: $cell_id/drive_id$

Explanation: The storage cell to which a cartridge was to be dismounted is full although the database indicates it is empty. The robot will retry the dismount until it finds an available cell. The most likely cause for this error is that someone entered the LSM and moved a cartridge manually.

Variable:

- *cell_id* is the storage cell location indicated in the database.
- *drive id* is the identifier of the tape drive.

Action Required: You should perform an audit on the LSM to reconcile the database with the physical contents of the LSM.

372 N Source location empty: cell id

Explanation: A cartridge marked for ejection was not found in its storage cell when the robot went to move it to the CAP. The audit terminates. This error is most likely the result of a hardware failure in the robot.

Variable: *cell_id* is the identifier of the cell where the cartridge marked for ejection should have been.

Action Required: Check previous entries in the Event Log for additional information about the error. Use the proper LSM entry procedure and check the robot's hands for in-transit cartridges; remove any cartridges that you find there. Repeat the audit after varying the LSM back online.

376 N Drive *drive_id*: No cleaning cartridge available.

Explanation: The specified drive requires cleaning but no cleaning cartridges are available. The mount proceeds.

Variable: *drive_id* is the identifier of the tape drive.

Action Required: Add more cleaning cartridges, making sure these are compatible with the drive type. See "Defining Cleaning Cartridges" in the "Cleaning Transports" section of "Chapter 9: Cartridge Management" of the *ACSLS Installation*, *Configuration, and Administration Guide* for information about adding cleaning cartridges.

377 N mc mo error: Cleaning failed. Drive drive id

Explanation: The mount operation involving a cleaning cartridge failed.

Variable: *drive_id* is the identifier of the drive requesting the cleaning operation.

Action Required: Observe the associated error messages in the event log to determine the root cause of the failure.

383 N Cleaning cartridge vol id: Usage limit exceeded.

Explanation: Automatic cleaning of a drive has caused a cleaning cartridge to exceed its specified maximum usage. The cleaning cartridge will no longer be available for automatic cleaning selection.

Variable: *vol id* is the identifier of the cleaning cartridge.

Action Required: Eject the cleaning cartridge.

386 N Source location empty: cell id

Explanation: The LSM robot was unable to find the tape cartridge in the location indicated by the database. The request fails.

Variable: *cell_id* is the storage cell location indicated in the database.

Action Required: The most likely cause for this error is that someone entered the LSM and moved the cartridge manually. You should perform an audit on the LSM to reconcile the database with the physical contents of the library.

387 N Cartridge in *cell id*, unreadable label

Explanation: The LSM robot was unable to read the label of the cartridge found in the specified drive. The request fails.

Variable: *cell_id* is the storage cell location indicated in the database.

Action Required: Eject the cartridge. Correct the label problem and re-enter the cartridge.

400 N Volume record created for vol id.

Explanation: A cell or drive marked reserved is found to contain a tape cartridge that does not exist in the database. A record is created for the new volume. This message usually appears together with the drive (drive_id) readable, marked in use message.

Variable: *vol id* is the volume record that was created.

Action Required: We recommend that you perform an audit of the LSM to reconcile the database with the physical contents of the library.

405 N Table lookup failure m_id: m_id

Explanation: A message processing error occurred for a mount request. The mount is identified as incomplete due to some failure.

Variable: *m_id* is the mount request ID.

Action Required: If the problem recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

435 N Volume: vol_id may be jammed in drive: $drive_id$

Explanation: The specified volume is jammed in the specified transport.

Variable:

- *vol id* is the jammed volume.
- *drive_id* is the drive that contains the jammed volume.

Action Required: The jammed volume must be manually unloaded from the drive; if necessary, contact hardware support.

436 N Cartridge vol_id , new location $cell_id$

Explanation: This message reports the recording of a new location for the cartridge in the ACSLS database.

Variable:

- vol_id is the volume identifier of the volume that was moved.
- *cell_id* is the new location of the moved volume.

Action Required: None; this message is informational only.

437 N volume (vol_id) not in drive $(drive_id)$, deleted

Explanation: A drive marked as containing a tape cartridge is found to be empty. The volume record is deleted from the database.

Variable:

- vol id is the volume record that was deleted.
- *drive_id* is the tape drive that the database indicated contained the cartridge.

Action Required: We recommend that you perform an audit of the LSM to reconcile the database with the physical contents of the library.

439 N Unknown packet received, command command, identifier ipc id

Explanation: The ACSSA has received a message packet with an IPC identifier not found in the request queue. The ACSSA is unable to process the message.

Variable:

- command is the entry in the MESSAGE HEADER.
- *ipc_id* is the identifier assigned to this message (used to synchronize requests and responses).

Action Required: If the message occurs frequently, use the following procedure to shut down and restart the library server software at your earliest convenience:

- 1. From a Command Processor window, issue an idle request to place the library server in a quiescent state.
- 2. Login as the acsss user, and shut down the library server using the kill.acsss utility.
- 3. Restart the library server using the rc.acsss utility.

441 N cl ipc read() byte count < sizeof(REQUEST HEADER) = bytes

Explanation: An internal ACSLS failure occurred.

Variable: *bytes* is the number of bytes read before the failure.

485 N ipc read: shared block read failed, errno = error no

Explanation: An internal ACSLS failure occurred.

Variable: *error no* describes the failure.

Action Required: If the error recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

486 N cl ipc read: accept() failed, errno + error no

Explanation: While establishing communication between ACSLS processes, the receiving side was unable to accept an incoming connection from the sending side.

Variable: error_no is the error code returned from the system call to accept().

Action Required: None. Additional messages in the Event Log may report a failure in inter–process communication (IPC). If this problem recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

487 N cl ipc read: invalid byte count detected

Explanation: A packet that appeared to contain invalid data was received during communication between ACSLS processes.

Action Required: None. Additional messages in the event log may report a failure in inter–process communication (IPC). If this problem recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

528 N Invalid type type identifier

Explanation: The type identifier is in the wrong format or has an invalid value.

Variable: *type identifier* refers to an invalid type of identifier used by the operator across the network or ACSLS.

Action Required: Enter the correct format (see "Component Types and Identifiers" in the "General Command Syntax" section of "Chapter 13: Command Reference" of the *ACSLS Installation, Configuration, and Administration Guide*) and/or the correct identifier value.

530 N Invalid tag count file=number1 vs. code=number2

Explanation: An incorrect number of entries was found in the dynamic variables file.

Variable:

- *number1* is the number of entries found in the file.
- *number2* is the number of entries expected by ACSLS.

Action Required:

- Log in as acsss.
- run: dv print > filename.
- Save the dynamic variables file for StorageTek Software Support.
- Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

536 N cl ipc read: read() failed, errno = error no

Explanation: The receiving side was unable to successfully read input from the sending side during communication between ACSLS processes.

Variable: errorno is the error code returned from the system call to read ().

Action Required: None. Additional messages in the Event Log may report a failure in inter–process communication (IPC). If this problem recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

546 N LH error type = status

Explanation: This message indicates that ACSLS has received an abnormal status code from the library hardware.

Variable: *status* is the code being passed between functions.

Action Required: Observe the accompanying LH error type to determine the root cause of this message.

713 E EXEC SQL unable to delete volume *vol_id* because of database error

Explanation: ACSLS could not find a volume in the library and attempted to mark it deleted, but the ACSLS database interface returned an unusual status to the volumetable update. The database update failed.

Variable: *vol id* identifies the absent volume.

Action Required:

- 1. Stop ACSLS (kill.acsss).
- 2. Stop the database (**db_command stop**).
- 3. Kill any hanging ACSLS processes.
- 4. Restart ACSLS (one time).

42

5. If the problem persists, you need the help of ACSLS software support to verify that the table volumetable exists and that the "acsss" user has the proper permissions to update it. Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

886 N byte count(byte_count) too small for min packet size(min_size) ignored

Explanation: The ACSLM has received a message that is too small from a CSI or the ACSSA. The ACSLM did not attempt to interpret the message because it did not have enough information. This could be a problem with either the network or the software.

Variable:

- byte count is the number of bytes in the message.
- *min_size* is the minimum size of a valid, readable message.

Action Required:

- Make sure the problem is not caused by the network or an ACSAPI client.
- If the problem is not a network or ACSAPI client problem collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this

ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

890 N Severe Error (status), Exiting to ACSSS

Explanation: The ACSLM has encountered a fatal error, such as a database failure or an inconsistency in the library configuration. The ACSLM will automatically initiate recovery processing if it is able. If recovery fails, and if you determine that the problem is not being caused by your network or by your ACS API client software, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.. If recovery completes with a recovery incomplete status, there is no need to call; however, you should audit the libraries at your earliest convenience.

Variable: *status* is a message indicating the nature of the severe error.

Action Required: Check previous Event Log entries to determine the cause of the failure. Follow the suggested action for the associated message(s).

923 N Drive drive_id lookup failed.

Explanation: While performing Cartridge Recovery, a volume record was encountered with a status that indicated a drive association (e.g., in drive, mount or dismount activity). No record was found in the database for the drive that was recorded in the volume record.

Variable: *drive_id* is the specific drive identifier that was recorded in the volume record.

Action Required: None. Cartridge Recovery proceeds as if no drive were recorded for the volume.

928 N XDR message translation failure

Explanation: During a translation of a packet of data from one version (1, 2, 3, or 4 packet) to another version, the XDR (external data representation) translator detected an error.

Action Required:

- 1. Reboot the server system and see if the problem persists.
- 2. If it does, contact Central Software Support (CSS) with a CSI trace during the failure and the full event log during the CSI tracing.

935 N Initiation Started

Explanation: CSI initiation has been started.

Action Required: None. This message is informational only.

936 N Creation of connect queue failed

Explanation: The call to the cl_qm_init() or cl_qm_create() common library function has failed while trying to create the internal SSI address connection queue.

Action Required: Restart ACSLS by doing the following:

- 1. From a Command Processor window, issue an idle request to place the library server in a quiescent state.
- 2. Login as the acsss user, and shut down the library server using the kill.acsss utility.
- 3. Restart the library server using the rc.acsss utility.
- 4. If the error recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

937 N Creation of network output queue failed

Explanation: The CSI was unable to create the network output queue which is used for messages between the CSI and the SSI.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

938 N Initiation completed

Explanation: The specified process has completed initiation procedures.

Action Required: None. This message is informational only.

941 N Undefined message detected: discarded

Explanation: The CSI has encountered a message from the ACSLM or the Network Interface (NI) that cannot be delivered because of incorrect message format or a CSI failure. The message is discarded.

943 N Can't delete Q-id queue id, Member: member id

Explanation: The CSI is unable to delete a message in an internal queue.

Variable:

- queue_id is the identifier of the CSI connection queue.
- member_id is the identifier of the queue member it is trying to delete.

Action Required: If the error recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

945 N Invalid communications service

Explanation: This entry may indicate that neither environment variable for the two available communication services has been defined. These variables are CSI_TCP_RPCSERVICE and CSI_UDP_RPCSERVICE, which can be defined through acsss_config. See "Chapter 6: Configuring Your Library Hardware" in the *ACSLS Installation, Configuration, and Administration Guide* for information about using acsss_config. This message may also indicate that a request received from the SSI has incorrect values specified in the protocol-dependent portions of the CSI_HEADER.

Variable:

- CSI_TCP_RPCSERVICE is the TCP communication service variable.
- CSI_UDP_RPCSERVICE is the UDP communication service variable.
- acsss_config is the program used to configure your ACSLS environment.
- CSI_HEADER is the variable that specifies CSI protocols and values.

Action Required:

 Make sure that your communication service has been defined using acsss_config.

• If the problem still occurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

947 N Cannot send message message: discarded

Explanation: The CSI is unable to communicate with a client. The CSI discards the message after the appropriate number of retries with timeouts.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

948 N Can't get queue status Errno: error_no Q-id: queue_id, Member: member_id

Explanation: The CSI is unable to get status information.

Variable:

- error no is the system error number.
- queue id is the identifier of the CSI connection queue.
- *member_id* is the identifier of the queue member for which the CSI is seeking status information.

949 N Queue cleanup Q-id: queue_id.

Member: member id removed.

Explanation: The CSI has begun the process of purging old processes from its connection queue. The CSI routinely searches for processes older than CSI_CONNECT_AGETIME and purges them.

Variable:

- queue id is the identifier of the CSI connection queue.
- *member_id* is the identifier of the queue member it is trying to delete.

Action Required: None; this message is informational only.

950 N Can't locate queue Q-id: queue id, Member: member id

Explanation: The CSI is unable to find a specific member in an internal queue.

Variable:

- queue id is the identifier of the CSI connection queue.
- *member_id* is the identifier of the queue member it is trying to locate.

Action Required: No action is required if the queue member is dropped because it is older than the connection queue aging time (defined by the CSI_CONNECT_AGETIME environment variable). If this error occurs before connection queue aging time has elapsed, however, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

951 N Queue creation failure

Explanation: The CSI is unable to create its connection queue.

Action Required:

- 1. Restart ACSLS.
- 2. If the error recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

952 N Can't add member to queue Q-id: queue id

Explanation: The CSI was unable to put a client's return address on its queue.

Variable: *queue_id* is the identifier of the CSI connection queue.

Action Required: If the error recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

953 N Invalid procedure number

Explanation: A program is trying to use the CSI, but the program is not using one of the two valid procedure numbers. This is a programming error in the client application.

 $\bf 954~N$ Unsupported module type $module_type$ detected:discarded

Explanation: The ACSLM detected a request with an IPC_HEADER *module_type* not set to TYPE_CSI or TYPE_SA. The ACSLM will only process requests received from a client application through the CSI, or from a user through the ACSSA.

Variable: *module type* is the invalid entry.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

Explanation: The attempted TCP connection is not possible. This is an error in the client system network.

Variable:

- rpc_error_msg is a detailed error message generated by the RPC service itself. In most cases, this message will be Program number not registered, which indicates that either the CSI or the SSI is not running.
- error no is the system error number.
- Internet_add is the address of the client machine to which the reply is sent.
- port id is the port identifier.

956 N RPC_UDP client connection failed, rpc_error_msg , Remote Internet address: Internet add, Port: port

Explanation: The attempted UDP connection is not possible.

Variable:

- rpc_error_msg is a detailed error message generated by the RPC service itself. In most cases, this message will be Program number not registered, which indicates that the CSI or SSI is not running.
- Internet_add is the address of the client host, expressed as an unsigned long integer.
- *port* is the port number of the client where a connection was attempted.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

957 N Invalid network protocol

Explanation: An unsupported network protocol has been passed. This is a programming error in the client SSI.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

960 N Cannot reply to RPC message

Explanation: The CSI is unable to reply to an RPC message because the call to the svc_sendreply() function failed. This is an error in the client system network. See the Sun network programming manual.

964 N Unmapped previously registered RPC service.

Explanation: The CSI has been initiated. It notifies you that an RPC number previously assigned to the CSI still exists. The CSI unmaps this number and Svctcp_create() remaps to a new one as a normal part of the initiation.

Action Required: None; this message is informational only.

965 N Create of RPC TCP service failed

Explanation: The RPC call to the svctcp_create() function has failed.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

966 N Can't register RPC TCP service

Explanation: The call to the svc_register() function failed.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support. See the Sun network programming manual, *Remote Procedure Call Programming Guide*.

967 N Create of RPC UDP service failed

Explanation: The RPC call to the Svctcp_create() function failed

968 N Can't register RPC UDP service

Explanation: The call to the svc register() function failed.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

969 N Termination Started

Explanation: CSI termination has been started.

Action Required: None; this message is informational only.

970 N Termination Completed

Explanation: CSI termination has been completed successfully.

Action Required: None; this message is informational only.

971 N LH error type = LH_ERR_TRANSPORT_BUSY drive_id

Explanation: The identified drive is busy.

Variable: *drive_id* identifies the busy drive.

Action Required: None; this message is informational only.

975 N Invalid command

Explanation: The CSI received a request packet from the SSI with an unrecognizable command specified in the MESSAGE HEADER portion of the CSI REQUEST HEADER.

Action Required:

- Contact a representative of your ACSAPI client support organization.
- Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this

ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

976 N Invalid location type

Explanation: The CSI received a request packet from the SSI with an unrecognizable type specified in the *message_data* portion of the request.

Action Required:

- Contact a representative of your ACSAPI client support organization.
- Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

977 N Invalid type

Explanation: The CSI received a packet from the NI with either an unrecognizable TYPE in the IPC_HEADER portion of the CSI_REQUEST_HEADER or an unrecognizable IDENTIFIER *type* in the message packet.

Action Required:

- Contact a representative of your ACSAPI client support organization.
- Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

980 N Cannot read message from ACSLM: discarded

Explanation: The CSI detected a message from the ACSLM but is unable to read it.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

981 N Operating system error error no

Explanation: The CSI encountered an operating system error. This message is indicative of a problem with the operating system itself, not with the CSI or the library server.

Variable: *error_no* is the system error number; see your Sun OS documentation for a description.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

982 N Duplicate packet from ACSLM detected:discarded

Explanation: The CSI has received a duplicate IPC packet. It automatically drops the duplicate packet.

1005 N Insufficient packet size = bytes

Explanation: An internal ACSLS failure occurred.

Variable: *bytes* is the packet size.

Action Required: If the error recurs, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

Explanation: The ACSLM (library manager process) has received an unexpected IPC packet from another ACSLS process. This typically occurs when commands are cancelled because an outstanding request process (associated with the command) may still send packets back to the ACSLM before the request/command is completely cleaned up.

Variable:

- *line_number* is the location in the ACSLS code where the error was detected.
- *command* is the type of ACSLS command packet received.

Action Required: None; this message is informational only.

1017 N CAP cap id: Enter succeeded status

Explanation: An enter operation was successful.

Variable:

- cap id is the identifier of the CAP.
- *status* is the final status code of the enter command.

1021 N Initiation of CSI Failed

Explanation: CSI initiation failed.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

Explanation: The NI's communications mechanism is unable to accept a message from the CSI. The CSI discards the message after the appropriate number of retries with timeouts.

Variable:

- failure_msg. is the message text identifying the cause of the failure.
- *error no* is the system error number.
- Internet_add is the address of the client host, expressed as an unsigned long integer.
- port id is the port identifier.

Action Required: See the corresponding <code>failure_msg.</code> description for an explanation and suggested action. Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

Explanation: The ACSLS server was unable to reply to a client, and has exhausted its retry attempts. The reply packet will be discarded.

Variable:

- status is the final status code of the function.
- *error_no* is the system error number associated with the failure (which may not be meaningful to the ACSLS error).
- *Internet_add* is the address of the client machine to which the reply is sent.
- *port_id* is the client machine port to which the reply is sent.

Action Required: If client/server communications and requests are not being affected, no action is necessary. If those communications/requests are being adversely affected, StorageTek recommends that you do the following:

- First, have your network personnel determine if either the local net or traffic on that net is causing the problem.
- If the local net is not the cause, contact your client system software provider for help in determining why the client is not accepting response packets from the server.

1025 N Unexpected signal caught, value: signal

Explanation: The CSI received a signal that it did not expect.

Variable: *signal* is the signal value that the CSI has received.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1026 N Dropping from Queue: Remote Internet Address: Internet_add Port: port_id ssi_identifier: ssid Protocol: protocol_type Connect type: connection_type

Explanation: The ACSLS server was unable to reply to a client, and has exhausted its retry attempts. The reply packet will be discarded.

Variable:

- *Internet_add* is the address of the client machine to which the reply is sent.
- *port_id* is the client machine port to which the reply is sent.
- *ssid* is the identifier associated with the client–side network interface.
- protocol type is the network protocol being used.
- *connection type* is the network connect type.

Action Required: If client/server communications and requests are not being affected, no action is necessary. If those communications/requests are being adversely affected, StorageTek recommends that you do the following:

- First, have your network personnel determine if either the local net or traffic on that net is causing the problem.
- If the local net is not the cause, contact your client system software provider for help in determining why the client is not accepting response packets from the server.

Explanation: This tape cartridge was not found where ACSLS expected it, but either the home cell or the drive couldn't be examined during the recovery process. The volume record will remain in the database until ACSLS can examine all recorded locations for the cartridge and determine that it is not in any of these locations.

Variable:

- vol id is the volume identifier of the missing cartridge.
- cell_id is the storage cell location for this cartridge recorded in the database.
- *drive_id* is the tape drive containing this cartridge, as recorded in the database, or none.
- *location* identifies the cell, drive, or cell and drive that ACSLS could not examine.

Action Required: No action is required. The cartridge is recorded as being in a home cell or a drive that cannot be examined now. ACSLS will attempt to recover the cartridge when the LSM comes online or the drive is ready and communicating with the library. If ACSLS does not find the cartridge, the customer may perform an audit of the ACS to locate lost volumes.

1053 I Volume vol id was not found and will be deleted

Explanation: This tape cartridge's volume record is deleted from the database.

Variable: *vol_id* is the volume identifier of the missing cartridge.

Action Required: No action is required.

Explanation: This tape cartridge's volume record is deleted from the database

Variable:

- is the volume identifier of the missing cartridge.
- cell_id was the storage cell location for this cartridge recorded in the database.
- *drive_id* was the tape drive containing this cartridge, as recorded in the database, or none.

Action Required: No action is required. The customer may perform an audit of the ACS to locate lost volumes.

1139 W ACS: acs id port: port id Parity error

Explanation: A parity error occurred in communications between the ACSLS server and the LMU.

Variable:

- acs id is the ACS identifier.
- *port_id* is the identifier of the ACSLS-to-LMU port.

Action Required: None; this message is informational only. if this message recurs often or is adversely affecting completion of library requests, check the ACSLS-to-LMU cable connection.

1141 W ACS: acs id port: port id Read timed out

Explanation: A read timed out in communications between the ACSLS server and the LMU.

Variable:

- acs id is the ACS identifier.
- port id is the identifier of the ACSLS-to-LMU port.

Action Required: None; this message is informational only. if this message recurs often or is adversely affecting completion of library requests, check the ACSLS-to-LMU cable connection.

1145 W ACS: acs id No queue entry found

Explanation: This message indicates that a response was received from the LMU with error status but when ACSLS searched its work queue for the corresponding entry it could not find it. The actual cause is not determinable in this instance but could be as a result of data transmission error between the LMU and ACSLS or possibly a duplicate return message from the LMU.

Variable: *acs_id* is the ACS identifier.

Action Required: If the problem recurs, check the LMU logs for any hardware problems and if necessary obtain an LMU trace to aid your hardware service representative in diagnosing the problem.

1156 N Invalid character received, line = line number

Explanation: A data packet received from the LMU contains an invalid character. Valid characters are A:Z and 0:9.

Variable: *line_number* is the location in the ACSLS code where the error was detected.

Action Required: If the problem persists and the system does not recover, check cable connections between the LMU and the ACSLS server.

Explanation: A connection between the ACSLS server and the LMU failed to establish communications.

Variable:

- *acs id* is the ACS identifier.
- port id is the identifier of the ACSLS-to-LMU port.
- *line_number* is the location in the ACSLS code where the error was detected.

Action Required: Check the physical connection and cable between the specified port on the ACSLS server and the LMU.

Explanation: A communications error occurred between the ACSLS server and the LMU. The port is being reset to attempt to retry communications.

Variable:

- acs_id is the ACS identifier.
- port_id is the identifier of the ACSLS-to-LMU port.
- *line_number* is the location in the ACSLS code where the error was detected.

Action Required: None, if communications are successfully reestablished. If not, check the physical connections between the ACSLS server and the LMU. Also check the acsss_config setting of the ACS communications port.

1187 N Invalid or unknown media type found in transaction
Unpack LMU Message Transaction

Explanation: The LMU encountered an unknown or invalid media type associated with the object volume of the current library operation.

Action Required: Check the media type character on the physical label of the associated volume. If the media type character is garbled or missing, a new label should be attached to the volume. Multiple instances of this error may point to problems with the robotics vision system.

1292 N Volume vol_id: Found in cell/CAP/drive/recovery cell_id/CAP_id/drive_id/cell action

Explanation: This message is issued when a misplaced tape is found in the library.

Variable:

- *vol id* is the identifier of the volume that was found.
- *cell/CAP/drive/recovery* is the location type where the volume was found.
- cell_id/CAP_id/drive_id/cell is the identifier of the location where the volume was found. Note that, in the case of a volume being found in the playground area (recovery), only the word cell, not the cell_id, is output.
- action is either added if a volume record was created for it or recovered if this volume already had a volume record.

1377 Messages

The 1377 messages on pages 70 through 74 are LMU-generated and are sent to the Library Handler. The following explanations, variables, and actions apply to all 1377 messages.

1377 N mod_id mod_ver mod_line function ACS# lh_state error#error category: error code

Explanation: 1377 messages indicate an LMU or LSM error or warning.

Variable: *function* refers to:

- LMU error: Co_4400:st_parse_error.
- *ACS#* refers to the LMU that reported the error.
- *lh_state* is the state of the Library Handler when the error was received.
- *error* refers to the error category and error code of the message.
- *error_category* is the component or category in which the error occurred. The categories are the following:
 - o CAP procedure error
 - o Configuration error
 - o Drive error
 - o General procedure error
 - LMU hardware error
 - LMU logical error
 - o LMU parameter error
 - o LSM hardware error

- o LSM logical error
- o LSM robotics error
- *error_code* the given code within an error category.

Action Required: For all 1377 messages, do the following:

- 1. Read the *error_code* to see if the hardware is in an unexpected state. If it is, correct it. For example, if the LSM is offline, vary it online. If the CAP is open, close it.
- 2. If the *error_code* describes an error in the LMU or LSM, reissue the command.
- 3. If the problem persists, contact StorageTek Software Support. For more information, see *Requesting Help from Software Support*.

All 1377 error codes are listed below. Each of the following 1377 messages relates to a particular procedure or library component and is followed by several messages that could appear in that category.

1377 N mod_id mod_ver mod_line function ACS# lh state error# CAP procedure error:

CAP is not reserved
CAP is already reserved
CAP is in eject mode
CAP is in enter mode
CAP move is active
CAP door is open
CAP catalog is in progress
Cannot unlock CAP, CAP door is not fully latched
Cannot cancel enter on release request
Magazine is not present

1377 N mod_id mod_ver mod_line function ACS# lh state error# Configuration error:

LSM not in static configuration Drive does not exist Illegal cap id Panel id is not a drive panel

1377 N mod_id mod_ver mod_line function ACS# lh state error# Drive error:

Drive is not communicating
Drive is not operational
Outstanding request for drive
Drive is allocated
Drive already has a cartridge
Drive is online for diag request
Drive cannot load cartridge
LOAD or UNLOAD in progress

1377 N mod id mod ver mod line

function ACS# lh_state error# General procedure
error:

LSM is not ready LSM is in maintenance mode LSM is offline pending LSM is offline Drive is full LSM path is in maintenance mode Path rejected due to full PTP deadlock Bad recovery cartridge VOLSER Exceeded max concurrent requests QUIESCE HOST request in progress Prior QUIESCE HOST overridden Max VOLSER STATUS already active CANCEL pending against request Request cancelled VOLSER was unexpectedly readable Unable to read VOLSER VOLSERs do not match Cell is full Cell is empty Drive is empty Drive is active Drive is not rewound Cartridge is not mounted Media types do not match Media types and VOLSERs do not match Incompatible media/drive type Incompatible media/cell

1377 N mod_id mod_ver mod_line function ACS# lh_state error# LMU hardware error:

Transmit reject - no LSM at node Transmit reject - bad LSM ID

Transmit reject - LSM not communicating

Transmit reject - trans error Transmit reject - no ACK

Transmit reject - no LAN
Transmit reject - no memory

Transmit reject - buffer overflow

Transmit reject - no response Transmit reject - LSM offline

Transmit reject - CAP Unlock already active

Transmit reject - LMU is standby

1377 N mod id mod ver mod line

function ACS# lh state error# LMU logical error:

Unknown allocation request

Bad qualifier byte 0

Bad qualifier byte 1

Bad qualifier byte 2

LSM is online

Offline pend overridden

Unknown panel type

Internal logical problem detected

Pass-thru port cell full

Pass-thru port cell empty

Full mailbox

Allocation pend timed out

LSM command pend timed out

Connecting LSM path is unavailable for ${\tt unknown}$

reason

1377 N mod_id mod_ver mod_line

function ACS# lh_state error# LMU parameter error:

Bad primary LSM

Bad secondary LSM

Undefined option or modifier

Invalid LSM address

Invalid panel address

Invalid row address

Invalid column address

Invalid drive address

Invalid CAP row address

Invalid CAP column address

No cell at the specified address

Invalid label modifier

Invalid source modifier

Invalid source type

Invalid destination type

Beginning address > end address

VOLSER contains bad characters

Invalid request ID

Invalid transaction length

Invalid host ID

Response contains bad characters

Host ID does not match current

Duplicate sequence number active

Transaction type not "request" or "message acknowledgement"

Invalid request code to cancel

1377 N mod id mod ver mod line

function ACS# lh_state error# error_type LSM
hardware error:

LSM did not respond to request
CAP unlock solenoid has overcurrented
Unlock CAP failed
Lock CAP failed
Drive not communicating
Tape unit interface failure
Failed to transfer image

1377 N mod id mod ver mod line

function ACS# lh_state error# error_type
LSM logical error:

Wrong LSM in GET response Expected packet not received Wrong task ID in response Wrong function ID in response Wrong cell address in response LSM is offline (from LSM) Bad cell location (from LSM) Unknown ending status from LSM LSM returned invalid response Unexpected or out-of-sequence CAP message FAILURE ending status BUSY ending status Bad command Bad parameters in command Bad address type Bad panel, row or column Arm currently is reserved CAP currently is reserved First Master Pass-Thru-Port reserved Second Master Pass-Thru-Port reserved Playground currently is reserved Drive 0/0 currently is reserved Drive 0/1 currently is reserved Drive 0/2 currently is reserved

72

Drive 0/3 currently is reserved Drive 1/0 currently is reserved Drive 1/1 currently is reserved Drive 1/2 currently is reserved Drive 1/3 currently is reserved Drive 2/0 currently is reserved Drive 2/1 currently is reserved Drive 2/2 currently is reserved Drive 2/3 currently is reserved Drive 3/0 currently is reserved Drive 3/1 currently is reserved Drive 3/2 currently is reserved Drive 3/3 currently is reserved LSM is online LSM is in maintenance mode LSM is offline LSM access door is open LSM is not initialized Cell location does not exist Hand is full Hand is empty Drive is full CAP door is currently unlocked Can't unlock CAP in idle mode CAP door is open CAP door is already locked CAP is already in idle mode CAP is already in eject mode CAP is already in enter mode CAP is in enter mode, can't eject CAP is in eject mode, can't enter CAP door is not locked for idle Invalid drive panel address No drive installed at address Invalid drive command specifier Drive is in motion Unable to rewind drive Unable to unload drive Drive cannot honor write protect Drive currently reserved

1377 N mod id mod ver mod line

function ACS# lh state error# LSM robotics error:

Arm is not operational Hand is not operational PTP is not operational PTP does not exist CAP is not operational Elements not operational Failed robotics portion of MOVE Bad PUT Bad GET Bad REACH retraction Bad REACH extension error positioning PTP No hands are operational Drive didn't detect cartridge on PUT Failed targeting portion of MOVE REACH is in an unsafe position Failure on recalibration of cell

1392 N LSM *lsm id* offline

Explanation: The LSM is offline and is therefore unavailable for entering tape cartridges. If this message is logged during enter processing, the message means the LSM was varied offline with the force option while its CAP was being used for the enter.

Variable: *lsm* id is the identifier of the LSM.

Action Required: Vary the LSM online, then reissue the enter request.

1406 N Transport failure drive id

Explanation: A hardware failure occurred in the specified transport.

Variable: *drive_id* is the transport that failed. Action Required: Contact hardware support.

74

1418 N Server system idle.

Explanation: The ACSLM has been placed in the idle state by an operator and is unavailable for requests using library resources.

Action Required: None; this message is informational only.

1419 N Server system running.

Explanation: The ACSLM has been placed in the run state.

Action Required: None; this message is informational only.

1420 N CAP cap_id : Cartridges detected in CAP.

Explanation: Cartridges were detected in the CAP during a vary online operation or during library server initiation or recovery.

Variable: *cap_id* is the identifier of the CAP.

Action Required: Issue an enter request to unlock the designated CAP, then remove the cartridges from the CAP.

1421 N Drive drive id: Clean drive.

Explanation: The specified drive needs to be cleaned.

Variable: *drive id* is the identifier of the library drive.

Action Required: If Auto Clean is FALSE, mount a cleaning cartridge in the designated drive. If Auto Clean is TRUE, this message is informational only; the drive will be cleaned automatically prior to the next mount of the drive. For more information about cleaning cartridges, see Chapter of *ACSLS Administrator's Guide*.

1422 N Library configuration error.

Explanation: The library configuration specified in the database is not the same as the one defined in the LMU, or a component appears in the database, but fails to respond to LMU commands. This error causes the library server to terminate.

Action Required: Rerun acsss_config. Then run an audit. See "Chapter 6: Configuring Your Library Hardware" in the *ACSLS Installation, Configuration, and Administration Guide* for information about acsss config and running an audit.

1423 N Data base failure.

Explanation: An ACSLS process is unable to access the database. A database error code, indicating the reason for the failure, will also be written to the Event Log.

Action Required:

- Gather Informix database information (see "Diagnostic Information for Informix Database–Related Error Messages" on page five (5).
- Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1427 N Event log is full.

Explanation: The Event Log has reached the maximum size defined in the library server installation. Messages will continue to be added to the Event Log, but this message will be logged at one-minute intervals until you reduce the size of the log.

Action Required: If you wish to keep a copy of the current Event Log for archiving purposes, move it to another directory. The Event Logger will automatically create a new file when it logs the next message. For information on managing the Event Log, see "Chapter 11: Reporting and Logging" in the *ACSLS Installation, Configuration, and Administration Guide.*

1428 N Server system idle is pending.

Explanation: The ACSLM is in an idle-pending state and is therefore unavailable for requests using library resources.

Action Required: None; this message is informational only.

1429 N CAP *cap_id*: Place cartridges in CAP.

Explanation: The specified CAP is ready to receive cartridges, as part of an enter operation. This message is repeated at approximately two-minute intervals until the CAP door is opened.

Variable: *cap id* is the identifier of the CAP.

Action Required: Open the designated CAP door and place the cartridges in the CAP.

1430 N IPC failure on socket *socket_id*.

Explanation: The ACSLM or ACSSA cannot communicate with another library server software component.

Variable: *socket id* is the identifier of the failing socket.

Action Required: If you did *not* issue an idle force command *and* the problem recurs, shut down and restart the library server software. Use the following procedure:

- 1. From a cmd_proc window, issue an idle request to place the library server in a quiescent state.
- 2. Log in as the acsss user, and shut down the library server using the kill.acsss utility.
- 3. Restart the library server using the rc.acsss utility.
- 4. If the problem continues, report the error to software support. Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1431 N port port id: Library error, error type

Explanation: An error in the library hardware has been reported to ACSLS.

Variable:

- *port_id* is the identifier of the ACSLS—to—LMU port.
- *error_type* is the error received by the ACSLS server from the library (via the LMU).

Action Required: Report the error to your Customer Services Engineer (CSE) by calling 1-800- 525-0369. The CSE should check the library and related hardware components to determine the cause of the library failure.

1432 N Server System network interface timeout.

Explanation: Due to lack of client response, a timeout has occurred during network data handling. Data such as earlier requests you put in or system responses may have been lost.

Action Required:

1. Check the network connections on both the server system and the client system.

If these are intact, the error may be due to network activity or momentary load.

2. If the error persists, verify network operations.

1433 N component component id: Offline

Explanation: The specified component was varied offline.

Variable:

- component is the library component (for example, ACS).
- *component id* is the identifier of the library component.

1434 N component component Id: Online

Explanation: The specified component was varied online.

Variable:

- *component* is the library component (for example, ACS).
- component id is the identifier of the library component.

Action Required: None; this message is informational only.

1435 N Software process failure.

Explanation: A library request process failed. This may be due to either an error in request processing or an unexpected process termination. This error can be ignored if you just issued an idle force command.

Action Required: Retry the command and see if you get the same error. If you do, shut down and restart ACSLS:

- 1. From a Command Processor window, issue an idle request to place the library server in a quiescent state.
- 2. Log in as the acsss user, and shut down the library server using the kill.acsss utility.
- 3. Restart the library server using the rc.acsss utility.
- 4. We recommend that you perform an audit to reconcile the database with the physical contents of the library.

1436 N Server system recovery complete.

Explanation: Library server recovery completed successfully.

1437 N Server system recovery failed.

Explanation: Library server recovery failed.

Action Required: Check previous Event Log entries for additional information about the failure. Follow the suggested action for the associated error message(s).

1438 N LSM lsm id: In-transit cartridge recovery incomplete.

Explanation: The specified LSM failed to recover all in-transit cartridges during library server recovery.

Variable: *lsm_id* is the identifier of the LSM containing the in-transit cartridges.

Action Required:

- 1. Query the LSM to make sure there are empty cells in the LSM.
- 2. If there are not empty cells in the LSM, eject cartridges to free cell space. See "Chapter 9: Cartridge Management" in the *ACSLS Installation, Configuration, and Administration Guide* for information about ejecting cartridges.
- 3. Ensure that the CAP in the specified LSM is empty.
- 4. Vary the LSM offline, and then back online to attempt in-transit cartridge recovery.
- If this process is unsuccessful, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1439 N Server system recovery started.

Explanation: Library server recovery has been initiated.

1440 N CAP cap id: Remove cartridges from CAP.

Explanation: The specified CAP contains cartridges and is ready for the operator to remove them. This message is repeated at approximately two-minute intervals until the CAP door is opened.

Variable: *cap id* is the identifier of the CAP.

Action Required: Open the designated CAP door and remove the cartridges.

1441 N Server system network interface failure.

Explanation: The CSI has encountered a Remote Procedure Call (RPC) failure. Data such as earlier requests you put in or system responses may have been lost.

Action Required: Check previous Event Log entries for additional information about the failure. Follow the suggested action for the associated error message(s).

1442 N Pool *pool id*: high water mark warning.

Explanation: The number of volumes in the specified scratch pool is greater than or equal to the high water mark.

Variable: pool id is the pool identifier.

Action Required: None; this message is informational only. Unless cartridges are used from the pool or the high water mark threshold is reset, this message will be repeated when a volume is added to the specified scratch pool. See "Chapter 9: Cartridge Management" in the *ACSLS Installation, Configuration, and Administration Guide* for information on managing scratch pools.

1443 N Pool pool id: low water mark warning.

Explanation: The number of volumes in the specified scratch pool is less than or equal to the low water mark.

Variable: *pool id* is the pool identifier.

Action Required: Follow your company's procedures for adding scratch volumes unless it is not a problem to run out of scratch volumes. See "Chapter 9: Cartridge Management" in the *ACSLS Installation, Configuration, and Administration Guide* for information on managing scratch pools.

1444 N CAP cap id: No CAP available, waiting...

Explanation: Audit processing has completed, but a CAP is not available for ejecting cartridges.

Variable: The *cap_id* indicates which ACS does not have a CAP available.

Action Required: None. When a CAP is available, the cartridges will be ejected.

1445 N Drive drive id: Cleaned.

Explanation: The specified drive has been cleaned.

Variable: *drive id* is the identifier of the library drive.

Action Required: None; this message is informational only.

1446 N CAP CAP_id: CAP door is open.

Explanation: The CAP door has been opened.

Variable:

- *lsm id* is the LSM whose CAP door is open.
- *CAP id* is the identifier of the CAP whose door is open.

1448 N filesystem: Disk usage of current% pct exceeds limit of limit% pct.

Explanation: The available disk space in the indicated file system is about to run out. Appearance of this message is usually indicative of either:

- the Event Log filling up disk space because it has not been periodically reset
- the database journal files are filling up disk space because a database backup has not been periodically done.

Variable:

- *filesystem* is the name of the disk subsystem that is about to run out of space.
- *current* is the current percentage of disk space used in the filesystem.
- *limit* is the disk threshold above which this message is periodically issued.

Action Required: Take the following actions to free up disk space.

- 1. See "ACSLS Event Log" in "Appendix B: Troubleshooting" in the *ACSLS Installation*, *Configuration*, *and Administration Guide* for information about managing the Event Log size and rollover files.
- 2. See "Chapter 10: Database Backup and Restore" of the *ACSLS Installation, Configuration, and Administration Guide* for information about database backups and managing database redo log files.

1450 N Volume identifier vol id deleted

Explanation: The specified volume identifier has been removed from the ACSLS database. This typically occurs when volumes are ejected from the library. It may also occur when the specified volume is not found where it should be located (for example, because it was manually removed from the library).

Variable: *vol_id* is the volume identifier of the volume that was deleted.

Action Required: None. This message is informational only. However, if you believe the volume was deleted in error, then report the error to software support. Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1453 N CAP cap id: Enter operation status

Explanation: This message shows the status of an enter operation that is either in progress or completed.

Variable:

- *cap_id* is the identifier of the CAP.
- *status* is the current status of the enter operation and the CAP identified in the message.

Action Required: None; this message is informational only.

1463 N Unknown media type detected. Not Entered Validate volumes placed in CAP

Explanation: The media type of a volume found in the CAP is unknown to ACSLS and the volume will not be entered into the library.

Action Required: Remove the cartridge from the CAP and check the media–type character on the label. Make sure the label is readable and that it is associated with a valid tape device attached to the library. Multiple instances of this error may point to problems with the robotics vision system.

1732 I ACSLS database recovery successfully completed. Database has been restored to the point of the last backup plus any subsequent transactions recorded on the current disk.

Explanation: This message indicates that the recovery you ran is completed. The second part of the message can mean that all transactions were recovered *unless* you have the following conditions:

- You do not have a second disk, just a primary disk.
- Your primary disk was damaged and you ran a recovery.

Under these conditions, it is possible that not all transaction files were recovered after running the recovery. Chances are likely that redo logs were not applied since they were corrupted by the same problem that prompted the restore.

If you do have a second disk *or* you have only a primary disk that did not crash, it is likely that all transactions were restored.

Action Required: None.

1820 E Unable to kill scsilh.im, PID PID

Explanation: A scsilh process was still running (scsilh.im) when the product came up. This scsilh.im process must be killed before the product can come up.

Variable: *PID* is the process id for the scsilh.im image that is still running.

- 1. Kill the scsilh.im as acsss by running stopSCSILH.sh.
- 2. If stopSCSILH.sh does not work when run as acsss, run stopSCSILH.sh as root.
- 3. If stopSCSILH.sh fails when run as root, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1

 $\label{thm:messages} \mbox{ Messages manual). Then contact StorageTek Software Support.}$

1822 E Killing SCSILH process *PID* with SIGTERM failed on *error desc*, errno= *error no*

Explanation: A scsilh.im was still running when the product came up or was shut down. This scsilh.im process must be killed before the product can come up.

Variable:

- *function* is the function that found the error.
- *PID* is the process id of the process to be killed.
- *error_desc* is the Unix error description associated with *error_no* returned by kill.
- error no is the value of the Unix system error number

- 1. Kill the scsilh.im as acsss by running stopSCSILH.sh.
- 2. If stopSCSILH.sh does not work when run as acsss, run stopSCSILH.sh as root.
- 3. If stopSCSILH.sh fails when run as root, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1824 E Invalid driver_state *state* for Connect/Vary request ACS *ACS id port name*

Explanation: This error message indicates an ACSLS software error.

Variable:

- *function* is the function that found the error.
- *state* is the state of the driver, of the form STATE_<NAME_OF_STATE>.
- ACS_id is the identifier of the ACS receiving the request.
- *port_name* is the name of the port in the Connect/Vary request.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1826 E Cleanup of SCSILH failed, rerun stopSCSILH.sh manually, errno *error desc*

Explanation: An scsilh process was still running when the product came up or shut down. This scsilh process must be killed before the product can come up.

Variable:

- *function* is the function that found the error.
- *error_desc* is the Unix error description associated with the error returned by UNIX, system call, system.

- 1. Kill the scsilh as acsss by running stopSCSILH.sh.
- 2. If stopSCSILH.sh does not work when run as acsss, run stopSCSILH.sh as root.

3. If stopSCSILH.sh fails when run as root, call your StorageTek Software Support Representative (SSR). See *How to Request Help* for information.

1827 E Cleanup of SCSILH failed, rerun stopSCSILH.sh manually, return code return code

Explanation: A scsilh process was still running when the product came up or shut down. This scsilh process must be killed before the product can come up.

Variable:

- function is the function that found the error.
- return_code is the return code from the ACSLS shell script stopSCSILH.sh.

- 1. Kill the scsilh as acsss by running stopSCSILH.sh.
- 2. If stopSCSILH.sh does not work when run as acsss, run stopSCSILH.sh as root.
- 3. If stopSCSILH.sh fails when run as root, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1828 E ACS ACS_id: fork of SCSILH failed errno (error_no) error desc

Explanation: The UNIX system call fork had an error.

Variable:

- function is the function that found the error.
- ACS id is the ACS identifier.
- *error_no* is the value of the UNIX system error number returned by the UNIX fork system call.
- *error_desc* is the UNIX error description associated with the *error* number returned by UNIX, system call, fork.

Action Required: Restart ACSLS and if the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1829 E execl (program) failed, errno=error_desc

Explanation: The UNIX system call execl failed executing *program*.

Variable:

- function is the function that found the error.
- *program* the program that execl tried to execute.
- *error_desc* is the UNIX error description associated with errno returned by the UNIX execl system call.

Action Required: Restart ACSLS and if the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1830 E SCSILH did not start, acslh exiting

Explanation: This message refers to a fatal error in either ACSLS, SCSILH, or the UNIX system. The product will shut down as part of this message.

Variable: *function* is the function that found the error.

Action Required: Restart ACSLS. If ACSLS does not restart after three tries, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1831 E return code (return code) terminated scsilh.im

Explanation: SCSILH terminated without a signal. If this message occurred during shutdown of ACSLS, it is informational only. Otherwise, see Action Required below.

Variable: return code is the code returned by SCSILH.

Action Required: Restart ACSLS. If ACSLS does not restart after three tries, contact collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support. Please have return code available.

1880 E Drive *drive_id*: Unable to position on the drive, status: loaded

Explanation: The drive is loaded. The robot was unable to target on the drive.

Variable: *drive_id* is the drive identifier.

Action Required: Drive transport is reporting a problem. This could be due to the drive or to the robot. Do the following:

- 1. Contact a CSE to have the drive checked for a stuck tape.
- 2. If there are no problems in the drive, the CSE should check the LMU and LSM error logs for more information.

1907 E Unable to create bdb EOF file.

Explanation: An ACSLS utility cannot create a required end-of-file marker.

Action Required: Make sure that the /tmp directory has write permission for all users, then rerun the backup.

1908 E Unable to read files from backup device, dev.

Explanation: The rdb.acsss utility cannot read the backup files from the specified backup device.

Variable: *dev* is the backup device you specified.

Action Required: Rerun the restore operation, specifying a valid device with a valid backup file created by the bdb.acsss utility.

1909 E The backup device dev is not a good bdb backup from ACSLS release Please try again specifying a valid bdb backup.

Explanation: The rdb.acsss utility cannot verify that the specified backup files are valid.

Variable:

- *dev* is the backup device you specified.
- release is the ACSLS release you are running.

Action Required: You must restore the database from a backup created by the bdb.acsss utility from the same version of ACSLS (*release*) that you are running. Rerun the restore operation, specifying a valid device with a valid backup file created by the *release* version of the bdb.acsss utility.

1918 N Too many processes. With the current settings specified through acsss_config, ACSLS requires no_req_pro processes to be running simultaneously. Currently, your system limit allows only sys_limit_no_pro_user processes per user. Either lower the number of mount processes, persistent query processes, or transient processes, or else raise this system limit.

Explanation: Message is self-explanatory.

Variable:

- no req pro is the number of required processes.
- *sys_limit_no_pro_user* is the system limit on the number of processes per user.

Action Required: Do one or more of the following:

- Lower the number of persistent query processes through acsss_config
- Lower the number of mount processes through acsss config
- Lower the maximum number of transient processes through acsss config
- Raise the maximum allowable number of processes per user. (This is system-dependent.)

1970 W RPtimeout value for keyword is not numeric.

Explanation: In the \$ACS_HOME/data/internal/RPtimeout file the value for *keyword* was not all numeric data. This message will be followed by message 1974.

Variable: *keyword* represents the operation that has the corresponding timeout value.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1971 W RPtimeout value for keyword is not in range.

Explanation: In the \$ACS_HOME/data/internal/RPtimeout file the value for *keyword* was not in the range of 1 second to 24 hours. This message will be followed by message 1974. The default value for *keyword* will be used.

Variable: *keyword* represents the operation that has the corresponding timeout value.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1972 W Unable to find keyword in RPtimeout file.

Explanation: In the file, ACSLS was unable to find the *keyword*. This message is followed by message 1974, which will give the keyword.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1973 W Unable to open RPtimeout file.

Explanation: ACSLS attempted to open \$ACS_HOME/data/internal/RPtimeout, but was unable to do so. The default value will be used. This message is followed by message 1974, giving the *keyword*.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

1974 I Using default timeout value for keyword.

Explanation: This message follows message 1970, 1971, 1972, or 1973 to inform you that the default timeout value was used for the LH request type *keyword*.

Variable: *keyword* represents the operation that has the corresponding timeout value.

Action Required: None. Action applies to the message that preceded this one.

2000 E Failed to get queue member.

Explanation: Message was not retrieved from the message queue for removal.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2001 E Don't have read permission.

Explanation: The CSI does not have read permission on the csi ip switch.dat file.

Action Required: Use chmod to set permissions on the csc_ip_switch.dat file for read and write access for the user.

2002 E Can't open file errno=error no

Explanation: A failure of type *errno* occurred when the csi ip switch.dat file was attempted to be opened.

Variable: *error_no* is the system error number associated with opening this file.

Action Required: Check that the file csc_ip_switch.dat exists and is in the proper location: \$ACSLS_HOME/data/internal/client_config/

If both of these conditions are met and the problem still persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support. For more information about managing a dual-LAN client configuration, see "Managing a Dual–Lan Client Configuration" in the "Library Management" chapter of the ACSLS Installation, Configuration, and Administration Guide.

2003 E Invalid entry displayed line - line ignored

Explanation: The line displayed is an invalid entry and the line is ignored.

Variable: *displayed_line* is the invalid line that needs to be corrected.

Action Required: Correct the line displayed and restart ACSLS.

2004 E Duplicate addresses *displayed line* - line ignored.

Explanation: Duplicate primary and secondary addresses were entered into the csc ip switch.dat file.

Variable: *displayed_line* is the invalid line that needs to be corrected.

Action Required: Correct the line displayed and restart ACSLS.

2005 E Max number of (max no allowed) dual clients exceeded

Explanation: More than the maximum number of allowable dual clients was entered into the csc_ip_switch.dat file. Only the maximum number of dual clients is allowed.

Variable: max_no_allowed is the maximum number of allowable dual clients entered into the csc ip switch.dat file.

Action Required: Do not exceed the maximum number of allowable dual clients in the csc_ip_switch.dat file, or, if you need more clients, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2006 E Bad primary addr - bad conversion: displayed addr.

Explanation: The primary address entered into the csc ip switch.dat file is not an IP address format.

Variable: *displayed_addr* is the erroneous primary address displayed.

Action Required: Correct the displayed address in the csc ip switch.dat file and restart ACSLS.

2007 E Bad primary addr - not digital: displayed addr

Explanation: The primary address entered in the csc ip switch.dat file is not an IP address format.

Variable: *displayed_addr* is the erroneous primary address displayed.

Action Required: Correct the displayed address in the csc ip switch.dat file and restart ACSLS.

2008 E Bad secondary addr - bad conversion: displayed addr

Explanation: The secondary address entered in the csc ip switch.dat file is not an IP address format.

Variable: *displayed_addr* is the erroneous secondary address displayed.

Action Required: Correct the displayed address in the csc ip switch.dat file and restart ACSLS.

2009 E Bad secondary addr - not digital: displayed addr

Explanation: The secondary address entered in the csc_ip_switch.dat file is not an IP address format. The address is not digital.

Variable: *displayed_addr* is the erroneous secondary address displayed.

Action Required: Correct the displayed address in the csc ip switch.dat file and restart ACSLS.

2010 I path opened - DUAL PATH OPTION ACTIVATED.

Explanation: File (csc_ip_switch.dat) was opened and read successfully. Dual path function is activated.

Variable: path is the full path to the csc ip switch.dat file.

Action Required: None.

2011 E path opened - Dual Option Process Failure.

Explanation: A major process failure has occurred when trying to de-queue primary address packets.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2012 N LMU error: ACS: acs_id Invalid value found in transmission, value = character

Explanation: The ACSLS (library handler process) detected an invalid character in the transmission received from the LMU.

Variable:

- acs id is the ACS identifier.
- *character* is the invalid character detected in the transmission.

Action Required: If the request failed, reissue the request.

2014 N LMU error: ACS: acs_id Invalid lmu_mode lmu_mode.

Explanation: The ACSLS (library handler process) received a response packet from the LMU with an unrecognizable LMU code specified in *lmu_mode*.

Variable:

- acs id is the ACS identifier.
- *lmu_mode* is the LMU mode from which the response was received. The mode is one of the following: master, standby, or standalone.

2018 N LMU error: ACS: acs_id Invalid compatibility level compat level line = line number.

Explanation: An invalid LMU compatibility level was detected.

Variable:

- acs id is the ACS identifier.
- *compat level* is the invalid compatibility level detected.
- *line_number* is the location in the ACSLS code where the error was detected.

Action Required: None. This message is informational only.

2027 N ACS: acs id Switchover Recovery Complete.

Explanation: The ACSLH (library handler process) has completed processing of library requests that were affected by a switch LMU or LMU IPL.

Variable: *acs_id* is the ACS identifier.

Action Required: None. This message is informational only.

2028 N ACS: acs id New Master LMU.

Explanation: The ACSLS (library handler process) has received an unsolicited message from the LMU indicating that there is a new Master LMU.

Variable: acs id is the ACS identifier.

2029 N LMU error: ACS: acs id Invalid lmu name lmu name.

Explanation: The ACSLS (library handler process) received a packet from the LMU with an unrecognizable LMU name specified in the *lmu name* portion of the packet.

Variable:

- acs_id is the ACS identifier.
- *lmu name* is the name of the LMU from which the packet was received: A, B, or standalone.

Action Required: None. This message is informational only.

2030 N LMU error: ACS: acs id Invalid standby status standby status.

> **Explanation:** The ACSLH (library handler process) received a packet from the LMU with an unrecognizable LMU name specified in the *lmu name* portion of the packet.

Variable:

- acs id is the ACS identifier.
- standby status is the status of the LMU from which the packet

Action Required: None. This message is informational only.

2031 N ACS: acs id Standby LMU now communicating.

Explanation: The standby LMU is communicating to the specified ACS.

Variable: acs id is the ACS identifier.

2032 N ACS: acs id Standby LMU not communicating

Explanation: The ACSLH (library handler process) has received an unsolicited message from the LMU indicating that the Standby LMU is not communicating with the ACSLS server.

Variable: acs id is the ACS identifier.

Action Required: None. This message is informational only.

2034 N ACSLH: Request Recoverer: message

Explanation: This message usually displays when a software error occurs during a dual LMU switchover recovery or in the recovery period after a standalone LMU IPLs.

Variable: *message* gives a detailed description of the error.

Action Required: Have the error description from *message* available, and collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

Explanation: Issuing a vary port offline command to the last online master port is not allowed.

Variable: *port status* is the status of the port.

Action Required: None. This message is informational only.

2036 N Standalone LMU, cannot initiate switch.

Explanation: Issuing a switch LMU command to a standalone LMU is not allowed.

2037 N Standby LMU not communicating, cannot initiate switch.

Explanation: Issuing a switch LMU command when the standby LMU is not communicating is not allowed.

Action Required: None. This message is informational only.

2038 N ACS acs id has no LSMs configured; you may want to verify hardware configuration.

> **Explanation:** This message may appear in either of the following conditions:

• If you have a dual-LMU configuration and a switchover occurs during acsss config, it is possible to get this message when one of the LMUs IPLs during acsss config.

Variable: *acs id* is the ACS that has no LSMs configured.

Action Required:

• If you see this message during product configuration, verify all hardware configuration and all hardware connections. These connections include those to the server, from the LMUs to the LSMs, and between the LMUs in a dual-LMU configuration.

If all hardware connections are correct and acsss config still detects an empty ACS, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

If this message occurs with an LMU switchover during acsss config, rerun acsss config.

2041 W Could not find text 'text' in file filename

Explanation: Some expected text in the specified file was not found. The file could possibly be corrupted.

Variable: *filename* is the file. *text* is the text that was expected to be in that file.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2050 W Error processing command: command - error

Explanation: This message occurs when there is an error processing a command received within ACSLS.

Variable:

- *command* The command that caused the error.
- *error* The specific error that occurred.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2051 W Ipc error reading command: error

Explanation: There was an internal communication error when trying to read a command for processing.

Variable: *error* The error encountered during IPC.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2052 W Unable to get value for TRACE VOLUME dynamic variable

Explanation: There was an error retrieving the value for the TRACE VOLUME dynamic variable. This will result in possible inconsistent behavior with respect to volume tracing.

Action Required: Collect relevant ACSLS data (see "Gathering" Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2053 W Error trying to create volume statistics entry.error_desc.

Explanation: There was a problem when trying to create an entry in the LIB VOL STSTS file.

Variable: error desc Detailed error message describing the problem.

Action Required: Collect relevant ACSLS data (see "Gathering" Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2054 W Move to *cell id* failed cartridge recovery needed. Volume vol id may be stuck intransit.

> **Explanation:** Volume is stranded inside the LSM somewhere between its original source and destination.

Variable:

- *cell id* Destination cell address.
- *vol id* Volume identifier of stuck volume.

Action Required: Do either of the following:

- Manually remove tape from LSM then audit its cell and enter it.
- Vary offline force the LSM the volume is in, then vary the LSM online to force intransit recovery.

2055 W Error updating cell cell id state to full.

Explanation: There was an error in setting a dell's state to full. This may have resulted in an inconsistent ACSLS database.

Variable: *cell id* Cell address that had the error.

Action Required: Perform a subpanel audit of cell indicated to attempt to reconcile database.

2056 W Error update cell cell id state to empty.

Explanation: There was an error in setting a cell's state to empty. This may have resulted in an inconsistent ACSLS database.

Variable: *cell_id* Cell address that had the error.

Action Required: Perform a subpanel audit of cell indicated to attempt to reconcile database.

2057 W Error update cell $cell_id$ state to reserved.

Explanation: There was an error in setting a cell's state to empty. This may have resulted in an inconsistent ACSLS database.

Variable: *cell_id* Cell address that had the error.

Action Required: Perform a subpanel audit of cell indicated to attempt to reconcile database.

2058 W Idle command failed information.

Explanation: An attempt to idle a portion of the ACSLS server failed.

Variable: information Detailed information about failure.

Action Required: The server will still be functional but you should report the problem as it may be a symptom of a larger problem. Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2059 W Failed to close accept socket. Error: error

Explanation: There was an error when attempting to close an internal ACSLS communication mechanism.

Variable: *error* The error that caused failure.

Action Required: This error could indicate a one-time anomaly or it could be a symptom of a bigger, underlying problem. If this message appears one time with no other error messages, then it can be ignored. If it appears multiple times or with other error messages, then collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2060 W Database Error: error

Explanation: There was an error processing a transaction with the database used by ACSLS.

Variable: *error* The specific error that occurred with the database.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2061 W Invalid data found in command: *information*

Explanation: ACSLS detected some invalid data in an internal command structure.

Variable: information Detailed description of invalid data.

Action Required: Collect relevant ACSLS data (see "Gathering" Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2062 W Unexpected ACSLH result received by move: *information*

Explanation: An internal error occurred in the communication between ACSLS components.

Variable: *information* Detailed description of the unexpected result.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2063 E Internal error in processing the move command: *information*

Explanation: An internal error occurred while processing a move request.

Variable: *information* Detailed information about the error.

Action Required: Collect relevant ACSLS data (see "Gathering" Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2064 E Error getting LIB VOL STATS value: *explanation*.

Explanation: ACSLS was unable to read the value for the LIB VOL STATS dynamic variable. This may result in a failure to log volume statistic entries.

Variable: *explanation* Detailed information about the error.

Action Required: Rerun acsss config to attempt to turn on LIB VOL STATS and then attempt the request again. If the error persists, then collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2065 E Error creating record for Volume vol_id : information.

Explanation: An internal error occurred while attempting to update the ACSLS internal database record for the given *vol_id*.

Variable:

- vol id Volume identifier of the volume that failed to create.
- *information* Detailed information about the error.

Action Required: Attempt to audit the expected location of the volume. If that fails, then collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2066 E Unable to update status for Volume vol id: information.

Explanation: An internal error occurred while attempting to update the ACSLS internal database record for the given *vol id*.

Variable:

- *vol id* Volume identifier of volume that failed to create.
- *information* Detailed information about the error.

Action Required: Attempt to audit the expected location of the volume. If that fails, then collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2068 N move: volume ($vol\ id$) not found in cell (%s), deleted.

Explanation: When attempting to move a volume, the volume was not found in its home cell. The volume record is deleted from the database

Variable:

- *vol_id* Volume identifier of the volume that was not found.
- cell id Cell location.

Action Required: Audit the LSM to reconcile the ACSLS database with the contents of the LSM.

2069 N cl vol write failed: (vol id)\n

Explanation: The process failed to update the volume record in the database.

Variable: (vol_id) is the volume id for the volume record that failed to be updated in the database.

Action Required: Display the volume. Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2079 I Sending first response to client %s.

Explanation: The first response that is sent to a network client is displayed. The substitution variable (%s) is the IP address.

Action Required: None. This is an informational message.

2088 E Unable to shift transaction log file on secondary disk.

Explanation: The secondary disk manager is unable to create the transaction log file on the secondary disk. This is a database error.

Variable: None.

Action Required: Rerun the secondary disk manager (sd mgr.sh).

2107 N Cannot allocate environment handle.

Explanation: The ODBC call to allocate the environment

handle has failed.

Variable: None.

Action Required: The application has to be re-started; or

contact your System Administrator.

2108 N Cannot allocate database handle.

Explanation: The ODBC call to allocate the database handle

has failed.

Variable: None.

Action Required: The application has to be re-started. Contact

your System Administrator.

2109 N Cannot allocate statement handle.

Explanation: The ODBC call to allocate the SQL statement handle has failed.

Variable: None.

Action Required: The application has to be re-started. Contact your System Administrator.

2111 N Cannot free connection handle.

Explanation: The ODBC call to free database connection handle has failed.

Variable: None.

Action Required: None.

2112 N Cannot free environment handle

Explanation: The ODBC call to free the environment handle

has failed.

Variable: None.

Action Required: None.

2113 N Cannot fetch. Return code return_code

Explanation: The ODBC call to fetch a row from the query

result set has failed.

Variable: return code The error code number returned by

ODBC.

Action Required: The application has to be re-run. Contact

your System Administrator.

2114 N Error in preparing statement

Explanation: The ODBC call to prepare an SQL statement for

execution has failed.

Variable: None.

Action Required: The application has to be re-run. Contact

your System Administrator.

2115 N Cannot reset auto commit option

Explanation: The ODBC call to set/reset the automatic commit

option for all database transactions has failed.

Variable: None.

Action Required: The application has to be re-run. Contact

your System Administrator.

2116 N Attempt to database recovery was aborted by the user

Explanation: During database recovery, a warning message is prompted to the user for overwriting the current database. Database recovery cannot be interrupted once it starts. With this message the user has selected to discontinue with the database

recovery process.

Variable: None.

Action Required: None. This message is informational only.

2118 E Could not create the filename file.

Explanation: The file creation command failed. This message is logged when the installation program is unable to create the odbc.ini file. The installation program fails to create this file when any one of the following environment variables is not set:

- \$ACS_HOME
- \$INFORMIXDIR

• \$HW_PLATFORM

Variable: *filename*. The odbc.ini file.

Action Required: Check whether the above-mentioned variables are set. If these are not set, please reinstall ACSLS.

2122 E Informix database backup area unavailable.

Explanation: This error is logged when you select a backup directory that cannot be used for backup purposes. This can happen for the following reasons:

- The directory chosen is not available or could not be created
- The file permissions can not be altered for the directory

Action Required: Reinstall ACSLS and enter the correct directory name.

2123 I Extracting Informix configuration files. This will take approximately *num* minutes. This Informix configuration can support sites with up to *num* cells in the attached LSMS.

Explanation: This message is displayed during the installation of the product.

Variable: *num* The number of minutes or cells.

Action Required: None. This message is informational only.

2125 E Database gentle shutdown did not succeed.

Explanation: The db_command stop command performs a gentle shutdown of the database server. This error is logged when the command fails after 10 retries.

Action Required:

• If the error occurred during initial installation, reinstall the product and retry.

> If the existing database is corrupted, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2126 E Database forced shutdown did not succeed.

Explanation: The db command stop force command performs a gentle shutdown of the database server. This error is logged when the command fails after 10 retries.

Action Required:

- If the error occurred during initial installation, reinstall the product and retry.
- If the existing database is corrupted, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2128 E Informix Storage Manager server is not up.

Explanation: The db command ism start command starts the Informix Storage Manager (ISM) server. This error is logged when the command fails to start the server.

Action Required:

- If the error occurred during initial installation, reinstall the product and retry.
- If the existing database is corrupted, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2129 E Informix Storage Manager server is not shutdown.

Explanation: The db_command ism_stop command shuts down the Informix Storage Manager (ISM) server. When the command fails to shut down the server, then this error is logged.

Action Required:

- If the message occurred during initial installation, reinstall ACSLS and retry.
- If the existing database is corrupted, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2200 E Cannot create group informix.

Explanation: This error can occur only while installing the product on an AIX operating system. The installation program creates the Unix group named informix. It calls the Unix command mkgroup to create the group. This error is logged if the mkgroup command fails. Group ID # 106 should be available.

Action Required: Reinstall ACSLS after the problem has been corrected.

2201 E Cannot change informix group.

Explanation: This error can occur only while installing the product on an AIX operating system. The installation program changes the ID of the UNIX group named informix. It calls the UNIX command chgroup to create the group. This error is logged if the chgroup command fails.

Action Required: Reinstall ACSLS after the problem has been corrected.

2202 E Cannot create informix user.

Explanation: This error can occur only while installing the product on an AIX operating system. The installation program creates the UNIX user named informix. It calls the UNIX command mkuser to create the group. This error is logged if the mkuser command fails. User ID # 11 should be available.

Action Required: Reinstall ACSLS after the problem has been corrected.

2203 E Cannot create lib6 user.

Explanation: This error can occur only while installing the product on an AIX operating system. The installation program creates the UNIX user named 1 i b6. It calls the UNIX command mkuser to create the group. This error is logged if the mkuser command fails. User ID # 203 should be available.

Action Required: Reinstall ACSLS after the problem has been corrected.

2205 E Group file update (informix) failed: updates discarded.

Explanation: This error can occur only while installing the product on a Sun Solaris operating system. The installation program creates the UNIX group named informix. If the group name already exists, it tries to update the entry. This error is logged if the update fails.

Action Required: Reinstall ACSLS after the problem has been corrected.

2206 E Group file move (informix) failed: updates discarded.

Explanation: This error can occur only while installing the product on a Sun Solaris operating system. The installation program creates the UNIX group named informix. It tries to move the previous version of group file. This error is logged if the move fails.

Action Required: Reinstall ACSLS after the problem has been corrected.

2207 E Insufficient disk space available in *disk*. Need needed_space Kb. Have available_space Kb. You must
make at least needed_space Kb available in disk
before installing Informix.

Explanation: The installation program verifies the available disk space before commencing the installation. This message is logged if the disk where ACSLS is being installed does not have enough space to install Informix software.

Variable:

- *disk* The disk on which the ACSLS product is being installed.
- needed space The disk space needed to install Informix.
- available_space This indicates the space available on the disk.

Action Required:

- Make space in the chosen directory by deleting files,
- Choose another directory that has more disk space, then reinstall ACSLS

or

• Install a larger disk

2208 E Could not install informix.

Explanation: This error is logged when the Informix software installation fails. The cause can be one or several of the following:

- The directory chosen to install Informix is not writable.
- The disk specified for backups had insufficient space.
- The file sqlhosts is not available in the \$INFORMIXDIR/etc directory.
- Initialization of the shared memory failed.

Action Required:

- The directory chosen to install Informix is not writable. Choose a directory that has write access and reinstall ACSLS.
- If the installation is being done using tapes, the tape is bad and the extraction failed. Replace the media and reinstall ACSLS.
- The disk specified for backups had insufficient space on it. Increase the available disk space and reinstall ACSLS.
- The file sqlhosts is not available in the \$INFORMIXDIR/etc directory. Replace the media and reinstall ACSLS.
- Initialization of the shared memory failed. Reinstall ACSLS.

2209 W \$INFORMIXDIR exists, install will not overlay an existing informix subsystem. To re-install the informix software, exit install and remove the \$INFORMIXDIR directory structure.

Explanation: The installation program checks whether the Informix software has already been installed. If Informix is already installed, one more installations on top of it is not allowed.

Action Required:

• Delete the current installation of Informix and reinstall ACSLS.

or

• Continue with the installation. The earlier installation of Informix will be retained.

> 2210 E An ACSLS database already exists (lib6). Install will not overlay an existing ACSLS database. ACSLS WILL NOT WORK WITH A DATABASE CREATED BY ACSLS 5.x. Unless you are sure that this database was created by ACSLS 6.0 or greater, you are STRONGLY encouraged to export the old database and then remove it. To remove the old database, exit the install script and remove the informix dir directory hierarchy.

> > **Explanation:** This message will be displayed if the ACSLS database already exists.

Variable:

- cur rel Current release number
- informix dir The directory where the Informix database is going to be installed. Typically this will be \$ACS HOME/../informix/IDS7.3

Action Required: The installation program, after logging this error, displays the following prompt:

"Continue with install? (If you answer yes, the database area will be unchanged.

- Press yes if you are sure the database was created by ACSLS 6.0 or above.
- Press no if the database was created by ACSLS 5.x. Remove the \$INFORMIXDIR and run the install.sh script again.

2211 E program: Cannot connect to Informix. Status code (error code).

Explanation: The application encountered this error while trying to connect to the Informix Database. The possible causes are listed below:

- The .odbc.ini file is either corrupted, missing or inaccessible.
- The driver files are missing.
- The environment variable \$LD_LIBRARY_PATH does not point to the Informix library path.

Variable:

- program The name of the source file where the error was encountered.
- *error-code* The error code returned by the application on return from the SQLConnect ODBC function.

Action Required:

- Check to see whether the ..odbc.ini file is in the \$ACS_HOME directory.
- Check to see whether the variable \$ODBCINI is pointing to the \$ACS_HOME directory.
- Ask the System Administrator or StorageTek Support to verify whether the Informix ODBC driver files are present.
- Check to see whether the variable \$LD_LIBRARY_PATH includes \$INFORMIXDIR/lib, \$INFORMIXDIR/lib/cli, and \$INFORMIXDIR/lib/esql.
- If the problem persists, contact your system administrator or StorageTek Support with the *error-code*.

> **2213 I** Informix database configuration files backup successfully completed.

> > **Explanation:** During each backup, the critical Informix configuration files are also backed up. After the backup is completed successfully, this message is logged.

Action Required: None. This message is informational only.

2214 E Cannot initialize the Informix Storage Manager server.

Explanation: This message is logged when the installation of the product Informix Storage Manager (ISM) fails. This typically happens because of an existing installation of the Informix Storage Manager.

Action Required: Remove the \$INFORMIXDIR/ism directory and run the install.sh script again.

2215 E Error in granting permission to informix as Informix Storage Manager user.

> **Explanation:** The installation program specifies root and informix as the administrators for the Informix Server Manager. This message is logged when granting permission to informix fails. This can happen if the informix user does not exist.

Action Required:

- Check to see whether the UNIX user informix exists, otherwise create the UNIX user informix.
- Check the host name. If it is corrupted, correct it.
- Reinstall ACSLS.

2216 E Error in adding the device dev.

Explanation: During installation, the installation program registers the backup directories with Informix Storage Manager to be treated as backup devices. This message is logged when this process fails. This can happen for the following reasons:

- The backup directory does not exit.
- The backup directory is already mounted.
- Informix Storage Manager can support a maximum of four devices. If four devices have been mounted already, this error is logged.

Variable: *dev* The backup directory that is being registered as a backup device.

Action Required:

- Check to see whether the directory exists. If not, then create one with the same name and retry installation. If it exists, the permission should be 664.
- Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2217 E Error in labelling dev.

Explanation: During installation, the install program creates backup volumes. This message is logged when this process fails. This can happen if a volume with the same name already exists.

Variable: *dev* The backup directory which is associated with the backup volume.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2218 E Error in mounting dev.

Explanation: During installation, the install program creates and mounts backup volumes. This message is logged when mounting a backup device fails. This can happen for the following reasons:

- The device does not exist.
- The backup volume with which the device is associated does not exist.

Variable: *dev* The directory that is getting mounted.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2220 E Error in creating new devices.

Explanation: During installation of second disk, the backup directories are shifted to directories in the second disk. This message is logged when this process fails.

Action Required: Please refer to the sd_event.log and see the error message number logged before this error number in order to know the exact reason for failure. One of the following errors may be the reason for failure:

- Please refer to the following error numbers in the ACSLS 6.0 Messages manual for more details: 1581, 1516, 1569, 2227, 2229, 2230, 2216, 2217, and 2218.
- Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2221 I Secondary disk already installed.

Explanation: This message is logged while doing the second disk installation if a secondary disk has already been installed.

Action Required: When this error occurs, it means that a second disk is already installed and no action is required.

2222 I ACSLS miscellaneous files backup successfully completed.

Explanation: ACSLS miscellaneous file backup was successful.

Action Required: None. This message is informational only.

2225 E Error in turning mirror off for rootdbs.

Explanation: This message is logged while deinstalling the second disk.

Action Required: Contact your System Administrator or collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2226 I Second disk de-installation completed successfully.

Explanation: This message is logged when second disk deinstallation is completed successfully.

Action Required: This message is informational only. It will not appear if the installation fails.

2227 E Error in unmounting dev.

Explanation: This message is logged when an error occurs while installing or deinstalling the second disk. Also, the dismount fails if the backup device is in use by a backup or restore session.

Variable: *dev* The directory being dismounted.

Action Required:

- Check to see whether any backup process is running. If so, wait till the backup is completed.
- If the error was encountered while installing the second disk option, reinstall sd_mgr.sh.
- If the error was encountered while deinstalling the second disk option, reinstall sd_mgr.sh.

2228 E Unable to mirror dbspace on Secondary disk.

Explanation: As a part of the second disk installation, ACSLS mirrors the database on to the second disk in order to provide additional security for your data against failures. This message is logged if the process of mirroring fails.

Action Required:

- Make sure the path given for the second disk is a valid one.
- Make sure the proper permissions (667) are set for the mirror dbspace on the second disk.
- If the problem still persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2230 E Unable to remove the device dev.

Explanation: During installation of a second disk, the backup directories are shifted to directories in the second disk. In this process, the devices used with the primary disk are removed. This message is logged when this process fails.

Variable: *dev* The directory being removed.

Action Required:

- Check to see whether any backup process is running. If so, wait till the backup has completed.
- If the error was encountered while installing the second disk option, reinstall sd_mgr.sh.
- If the error was encountered while deinstalling the second disk option, reinstall sd_mgr.sh.

2231 E Could not install Informix Storage Manager.

Explanation: As a part of the product installation, the Informix Storage Manager (ISM) also gets installed. If the installation was unsuccessful, then this message is logged. The possible causes for failure are listed below:

- The environment variable \$INFORMIXDIR is not set
- The environment variable \$INFORMIX_BACKUP_DIRECTORY is not set.
- The installation creates the backup directory structure. The permissions to these directories are insufficient.
- Another instance of ISM is running in the background
- If the installation program found that the ISM had already been installed, it attempted to remove the previous installation and failed.
- As a part of the installation, the script tried to initialize the ISM server and failed.
- The backup devices could not be assigned to the backup volumes.

Action Required: Please refer to /tmp/install.log to judge the exact point of failure. The action could be one of the following:

- If the failure is due to corruption or absence of environment variables, please log out and login again. ACSLS automatically reloads the variables at the time of login.
- Contact your System Administrator or StorageTek Support to ensure that sufficient permissions are granted to the backup directories you have chosen.
- If another instance of ISM is running in the background, please ask your System Administrator or have StorageTek Support assist you in killing that instance, then reinstall the product.

- Try to reinstall ACSLS.
- Please refer to the following error numbers in this book for more details: 1516, 1476, 2129, 2243, 2214, 2215, 2216, 2217, and 2218.

2232 E Informix is installed on disk informix par. The directory for second disk support must be on a different disk. The following is the output from the UNIX df command: *output*.

> **Explanation:** The directory specified for second disk support lies in the same partition as that of the primary disk. To avoid complete loss of data and backups in the event of disk crash, it is essential that the backups are on another disk.

Variable:

- *informix par* The name of the disk on which Informix is installed.
- *output* The output from the df command.

Action Required: Reinstall ACSLS, specifying a disk volume that is different from the one in use by the Informix installation.

2233 N program: Cannot set ODBC driver version. Status code (error code).

> **Explanation:** An internal error happened while ACSLS was trying to connect to the database.

Variable:

- program This is the name of the source file where the error was encountered.
- *error code* The error code encountered by the application on return from the SQLSetEnvAttr ODBC function.

Action Required: Reboot the server and retry (suspecting memory to be the reason).

2234 I Informix database backup started.

Explanation: Informix started the database backup process.

Action Required: None. This message is informational only.

2236 I Informix database backup successfully completed.

Explanation: Informix successfully completed the backup of the database.

Action Required: None. This message is informational only.

2237 E EXEC SQL delete from audittable.

Explanation: An attempt to delete the rows from the audit table has failed.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2238 E directory doesn't have sufficient disk space for Informix second disk support. directory has available space Kb available. A minimum of minimum space Kb is required. The following is the output from the UNIX df command.

> **Explanation:** The directory specified for second disk support does not have sufficient free space.

Variable:

- directory The name of the directory specified for second disk support.
- available space The amount of space available on that directory.

• *minimum_space* The minimum amount of space required for second disk support.

Action Required: Create at least *minimum_space* KB of space in the directory specified or specify a different directory which has the minimum required space on it.

2240 E Unable to configure volume backup data volume.

Explanation: As a part of the manual backup, the backup files are archived to a tar file. During this process, the backup devices are configured to disallow backups until the archival is complete. This message is logged if an error occurs while configuring the backup devices.

Variable: backup data_volume The backup volume that could not be configured. Volume names suffixed with pri_indicate that they are primary disk volumes. Similarly, volume names suffixed with sec_indicate that they are secondary disk volumes.

Action Required: Please log out, log in as acsss and retry the second disk installation/deinstallation.

2241 E Failed to reset logfile name.

Explanation: During the course of time, some of the key Informix log files keep growing in size. In order to prevent this uncontrolled growth, these files are moved to backup files periodically.

Variable: *logfile_name* The name of the log files being moved.

Action Required: Ensure that you are logged in as the correct user to execute this utility.

- Check the file access permissions for these files.
- Check the user permissions for these files. They should be 667.
- If you find that the variable \$ACS_HOME was accidentally erased, please log out and log in again.

2242 I Informix database recovery started.

Action Required: Explanation: Informix has begun the recovery of the database.

Action Required: None. This message is informational only.

2243 E Cannot remove the directory directory.

Explanation: Deletion of a directory may have failed due to access permission problems.

Variable: directory The directory being deleted.

Action Required: Ensure that you are logged in as the correct user to execute this utility. Check the access permissions for the directory.

2245 E Unable to configure Informix Storage Manager retention period.

> **Explanation:** The attempt to change the retention period of the backups failed. This typically happens either during installation or while changing the retention period using the configuration script acsss_config.

Action Required: Restart the installation or configuration. If the error still persists, contact your System Administrator or collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2246 E Failed to add neccessary CRON entry for automatic backup.

Explanation: The automatic backup configuration script registers the periodic backup event with the Operating System Scheduler. This error is logged when the registration failed.

Action Required: Contact your System Administrator or collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2248 E Informix database backup failed.

Explanation: The backup of the Informix database has failed. The failure may be due to the following reasons:

- The Informix Server Manager utility onbar failed to back up.
- After the backup, a verification is done to check whether the backup files are error–free. The backup process aborts if the verification fails.
- There was not enough space on the backup disk.

Action Required:

- Check the acsss_event.log for presence of error code 2256. This indicates that the problem was due to lack of disk space. Execute the script acsss config to decrease the backup retention period.
- If the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.
- 2250 I ACSLS database recovery successfully completed. Database has been restored to the point of the specified backup.

Explanation: This message is logged after successfully restoring from a previous local disk backup.

Action Required: None. This message is informational only

2253 I Informix database configuration files backup started.

Explanation: The backup process automatically backs up critical Informix database configuration files. This message is logged when the backup of these files is started.

Action Required: None. This message is informational only.

2254 E Informix database configuration files backup failed.

Explanation: The backup process automatically backs up critical Informix database configuration files. The backup of these configuration files has failed. This could be due to the following reasons:

- The Informix database configuration files were not present in the directory \$INFORMIXDIR/etc.
- The contents of the variable \$INFORMIXDIR were altered accidentally.
- The files are copied to the directory \$INFORMIX_BACKUP_DIRECTORY/misc. The write permission to this directory has been removed.

- Reinstall ACSLS if any product files are missing.
- Please log out of the session and login again. ACSLS reloads all the variables. If the error occurred because the environment variables got altered accidentally, the reloading will set it right.
- Ask your System Administrator to verify the permissions to the directory \$INFORMIX_BACKUP_DIRECTORY/misc. The permission should be 667.

> 2256 I Disk is percentage full, please decrease the database backup retention period to free disk space.

> > **Explanation:** The disk used for backup is running out of space. If expired volumes are not removed, there is a very high possibility of the backup disk overflowing. As a result, the automatic backup could fail to back up your data.

> > Variable: percentage The percentage indicating the amount of the disk space already used.

- Run the acsss_config script.
- Select the option 5: Set automatic backup parameters.
- Reply **n** for the prompt Would you like to modify the automatic backup settings? (y or n):
- Using the next prompt, set the retention period to a lower value. This setting automatically deletes expired backups, thereby releasing locked up disk space.

> **2257 E** Unexpected error occured in automatic configuration settings.

> > **Explanation:** The script that allows the user to configure the automatic backup parameters has failed. The failure may be due to the following reasons:

- The variable \$ACS_HOME points to an incorrect directory.
- This script depends upon another script \$ACS_HOME/.acsss_env. That script is missing.
- Could not find script fix_autobkup_cron.sh.
- The configuration program registers your auto backup settings with the Operating System Scheduler. This process failed.

- Please log out of the session and log in again. ACSLS reloads all the variables. If the error occurred because the environment variables got altered accidentally, the reloading will set it right.
- Reinstall ACSLS if any product files are missing.
- Execute the script acsss_config to configure the auto-backup parameters.

2258 E Expired backup files could not be removed.

Explanation: ACSLS removes expired backup files prior to initiating a backup in order to avoid overfilling the backup disk. This message indicates that the recycling of the expired files could not be completed successfully.

This can happen if:

- The environment file \$ACS_HOME/.acsss_env is not found.
- Environment variable RETENTION_PERIOD is not set.
- The variable \$INFORMIX_BACKUP_DIRECTORY was altered or erased.
- The variable \$INFORMIX_BACKUP_DIRECTORY points to an incorrect directory.
- There is no permission to delete files in the directory pointed to by \$INFORMIX_BACKUP_DIRECTORY.

- Log out of the session and log in again with the correct user ID. ACSLS reloads all the variables. If the error occurred because the environment variables got altered accidentally, the reloading would set it right.
- Reinstall ACSLS if any product files are missing.
- Contact your System Administrator or collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2259 I Recycle of expired files completed.

Action Required: ACSLS removes expired backup files prior to initiating a backup in order to avoid overfilling the backup disk. This message indicates that the recycling of the expired files was completed successfully.

Action Required: None. This message is informational only.

2260 I Informix configuration files have been restored.

Explanation: The recovery of the Informix configuration files has been completed successfully.

Action Required: None. This message is informational only.

2261 I Backup of ACSLS miscellaneous files started.

Explanation: The backup of the miscellaneous files used by the ACSLS product is being started.

Action Required: None. This message is informational only.

2262 W Failed to recycle expired files.

Explanation: An internal error occurred while trying to recycle expired backup files.

Action Required: No action required.

2263 E Failed to clear sysutils database.

Explanation: An internal error occurred while trying to clearing sysutils database.

Action Required:

• If the database is not already up, bring it up using:

db command start

Login as root.

Run the script:

\$INFORMIXDIR/etc/clear sysutils.sh.

- If the script runs successfully, manually backup the ACSLS database using bdb.acsss.
- If the script does not run successfully, save the messages reported on the screen, and collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2270 E Cartridge stuck in in-transit cell. Please vary LSM lsm id offline and back online again to recover the cartridge.

> **Explanation:** A cartridge is stuck in the in–transit cell of LSM with identifier lsm id.

Variable: *lsm* id is the LSM identifier.

Action Required: Vary the LSM specified in the message offline and back online to recover the cartridge.

2271 E LSM *lsm id* in maintenance mode.

Explanation: The LSM with the specified *lsm id* is in maintenance mode.

Variable: *lsm* id is the LSM identifier.

- Record any status information displayed on the Library.
- IPL the LSM. In ACSLS, vary the LSM online.
- If the problem persists, call your StorageTek Customer Service Engineer (CSE).

2272 I Micro-code had been changed in LSM lsm id.

Explanation: The microcode level for the LSM with identifier *lsm id* has been changed.

Variable: lsm id is the LSM identifier.

Action Required: None. This message is informational only.

2273 E Pass-thru port inoperative in LSM lsm id.

Explanation: The pass—thru port in LSM with identifier *lsm id* is inoperative.

Variable: *lsm id* is the LSM identifier.

- Record any status information displayed on the Library.
- IPL the LSM. In ACSLS, vary the LSM online.
- If the problem persists, call your StorageTek Customer Service Engineer (CSE).

2274 E LSM *lsm id* Not Ready. Manual Intervention Required.

Explanation: The LSM with identifier *lsm id* is not ready. Possible reasons are that a door is open or a cartridge is stuck in the LSM hand.

Variable: *lsm_id* is the LSM identifier.

Action Required:

- Check the LSM hand and manually remove cartridge.
- Be sure the LSM door is closed.

2275 E Cartridge stuck in pass-thru port. Please vary any LSM in ACS acs id offline and back online again to recover the cartridge.

> **Explanation:** A cartridge is stuck in the pass–thru port of ACS acs id. Vary any LSM in the ACS specified in the message offline and back online to recover the cartridge.

Variable: *acs_id* is the ACS identifier.

Action Required: Vary any LSM in the ACS specified in the message offline and back online to recover the cartridge.

2276 W LSM lsm id could not recover volume vol id.

Explanation: One of the LSMs could not recover a cartridge.

Variable:

- *lsm id* is the LSM identifier.
- vol_id is the Volume identifier of the cartridge.

Action Required: None. The cartridge will probably be recovered by the other LSM of the L700e pair while coming online.

2277 I LSM *lsm_id* received Unit Attention Sense: *sense_code* (*sense desc*).

Explanation: A SCSI device has returned a Sense Code for the LSM *lsm_id*.

Variable:

- *lsm id* is the LSM identifier.
- sense_code is the Sense Code returned by the SCSI device.
- sense_desc is a brief description of the sense code returned

Action Required: None. This message is informational only.

2278 W LSM *lsm_id* received Sense: *sense_code* (*sense_desc*).

Explanation: A SCSI device has returned a Sense Code for the LSM *lsm id*.

Variable:

- *lsm_id* is the LSM identifier.
- *sense_code* is the Sense Code returned by the SCSI device.
- sense_desc is a brief description of the sense code returned.

- Record any status information displayed on the Library.
- IPL the LSM. In ACSLS, vary the LSM online.
- If the problem persists, call your StorageTek Customer Service Engineer (CSE).

2280 E DB status [err num] detected on delete from clienttable

Explanation: An attempt to delete a client record from the database has failed.

Variable: *err num* is the error number.

Action Required:

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2281 E Exec SQL lock timeout on delete from clienttable.

Explanation: An attempt to delete a locked client record from the database has failed.

Action Required:

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2283 E Unexpected resource type *rsc type* and resource status rsc status

> **Explanation:** An unexpected match of resource type and resource status is detected.

Variable:

- rsc type is the value of resource type.
- rsc status is the value of resource status.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2284 I Status of *lib cmpnt cmpnt id* is changed to *status*.

Explanation: Status of a library component, e.g., LSM, CAP or DRIVE with an identifier cmpnt id, e.g., 0,0(lsm_id) or 0,0,0(cap_id) or 0,0,7,1(drive_id) is changed to status.

Variable:

- *lib cmpnt* is library component type, e.g., LSM, DRIVE, or CAP.
- cmpnt id is the identifier of a library component, e.g., 0,0(lsm_id), 0,0,0(cap_id), or 0,0,7,1(drive_id).
- *Status* is the new status value.

Action Required: None. This message is informational only.

2285 E Invalid lib cmpnt cmpnt id received in a message from module type; dropping message

> **Explanation:** This message indicates that acsmon received a message that included an invalid component identifier. The message is dropped, and normal processing continues.

Variable:

- *lib cmpnt* is the library component type, e.g., LSM or DRIVE
- cmpnt id is the identifier of a library component, e.g., 0,0(lsm_id) or 0,0,7,1(drive_id)

> • module type is the name of the module that sent the message

Action Required: Collect relevant ACSLS data (see "Gathering" Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2287 I Serial number of *lib cmpnt cmpnt id* changed to *serial num*.

Explanation: This message is to indicate that there is a serial number change for a library component, e.g., LSM or DRIVE with an identifier *cmpnt id*, e.g., 0,0(lsm_id) or $0,0,7,1(drive_id).$

Variable:

- *lib cmpnt* is library component type, e.g., LSM or DRIVE.
- cmpnt id is the identifier of a library component, e.g., $0.0(lsm_id)$ or $0.0.7.1(drive_id)$.
- *serial num* is the new serial number.

Action Required: None. This message is informational only.

2288 E EXEC SQL failed to create *table name*, error = *err num*

Explanation: An ODBC call to prepare an SQL statement for creating a table table name has failed.

Variable:

- *table name* is table name to be created.
- *err num* is the error number returned by ODBC.

- Restart the database and see if the problem persists.
- If it does, contact your System Administrator.

2289 E DB status [err_num] detected on delete for client id client id

Explanation: An attempt to delete a client record from the database has failed.

Variable:

- err num is the error number.
- *client id* is the identifier of the client to be deleted.

Action Required:

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2290 E EXEC SQL lock timeout on delete from clienttable where client_id = $clnt_id$

Explanation: An ODBC call to prepare an SQL statement for deleting a client record from clienttable has failed.

Variable:

clnt id is an identifier of the client to be deleted.

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of

> this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2291 E EXEC SQL delete from clienttable failed, where client id = clnt id

> **Explanation:** An attempt to delete a locked client record from clienttable has failed.

Variable:

clnt id is the identifier of the client to be deleted.

Action Required:

- Restart the application server and see if the problem
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2292 E EXEC SQL select client id clnt id from clienttable failed

Explanation: An ODBC call to prepare an SQL statement for selecting a client record(s) from clienttable has failed.

Variable:

clnt id is the identifier of the client to be deleted.

- Restart the application server and see if the problem
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of

> this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2293 E EXEC SQL failed to open cursor.

Explanation: An ODBC call to prepare an SQL statement for opening a cursor has failed.

Variable:

cursor is the database handle for executing SQL statement.

Action Required: Action Required: The application has to be re-started. Contact your System Administrator.

2295 I Starting automatic backup to local disk.

Explanation: This message is displayed when you opt not to take backup on to a tape while exiting from rdb.acsss. In this case, an automatic backup to local disk is triggered.

Action Required: None. This message is informational only.

2297 W Informix Database Space is percentage full, please contact StorageTek Support.

> **Explanation:** This message is logged when the database space exceeds 85% of its capacity. An hourly cron job checks the database space. So once you see this message, you will see this again every hour until more database space is allocated.

Variable: percentage The percentage indicating the amount of database space file already used.

Action Required: For guidance on allocating more space to the existing database space, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

> ${f 2298}$ W ACSLS is running. To stop the database, ACSLS must first be shutdown using 'idle' and 'kill.acsss'. Exiting.

> > **Explanation:** This error is logged when you try to stop the database while ACSLS is running. This is not allowed since the application communicates extensively with the database. Hence, the ACSLS application must be shut down prior to shutting down the database.

- Stop ACSLS by executing the commands idle and kill.acsss.
- Shut down the database server using db_command stop.

> 2299 W ACSLS is running. To run rdb.acsss, ACSLS must first be shutdown using 'idle' and 'kill.acsss'. Exiting.

> > **Explanation:** This message is logged when you try to recover the database using rdb.acsss while the ACSLS application is running.

Action Required:

- Stop ACSLS by executing the commands idle and kill.acsss.
- Shut down the database server using db_command stop.

2303 E getenv failed for \"LSPID_FILE\" in mod_id at line line_number.

> Action Required: An attempt to get the environment variable LSPID_FILE, which would indicate ACSLS is running, has failed.

Variable:

- mod id is the name of the module issuing the error message.
- line number is the location in the ACSLS code where the error was detected.

Action Required: None. The program exits after issuing the message.

> **2304 E** stat failed for \${LSPID FILE} in mod id at line line number. errno is error no: error

> > **Explanation:** An attempt to locate the /tmp/acsss.pid file has failed. ACSLS can not run properly without this process.

Variable:

- mod id is the name of the module issuing the error
- *line number* is the location in the ACSLS code where the error was detected.
- error no is the error number returned if the /tmp/acsss.pid file doesn't exist.
- error is the text of the error message for error no.

Action Required: None. The program exits after issuing the message.

2305 I ACSLS must be running to execute command

Explanation: The command that was entered can not run without an active ACSLS session.

Variable: command is the command that was entered by the user.

Action Required: None. The program exits after issuing the message.

2306 I Volume found in the library. Unable to delete, use EJECT.

Explanation: A manual volume delete request failed because the volume to be deleted was located by the Cartridge Recovery component. Manual volume delete can not be used to delete a verifiably present volume in an active LSM. In such a case, EJECT should be used to remove tapes from an LSM.

Action Required: None. The program exits after issuing the message.

2307 W Cartridge Recovery could not examine all recorded locations for this volume.

Explanation: The Cartridge Recovery component was unable to catalog a library location where the requested volume may reside. This can be due to an offline LSM or a non-communicating drive. User confirmation is required to delete these volumes. This message is issued in conjunction with MSG 2308 below. This message is suppressed and confirmation assumed if the -n (no_confirm flag) was included in the original manual volume delete message.

Action Required: None. The program exits after issuing the message.

2308 I Do you really want to delete volume *vol_id* from the database? [yes|no]

Explanation: A request for user confirmation is issued whenever the Cartridge Recovery component can not examine all possible library locations for the volume (see MSG 2307 above). This message is suppressed and confirmation assumed if the -n (no_confirm flag) was included in the original manual volume delete message.

Variable: *vol_id* is the volume serial number requested for deletion.

2309 E : md proc init failure: status = status

Explanation: The function to register this process for error logging failed.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_ipc_create().

Action Required: None. The program exits after issuing the message.

2310 E mod id: atexit failure: errno = error no: error msg

Explanation: This message is issued for a failed attempt to register the database disconnect or ipc destroy wrapper functions to be executed at the time the manual volume delete process exits.

Variable:

- mod id is the name of the module issuing the error message.
- error no is the error number returned if the /tmp/acsss.pid file doesn't exist.
- error msg is the text of the error message that corresponds with error no.

Action Required: None. The program exits after issuing the message.

2311 E mod id: cl db connect failure: status = status

Explanation: The program was unsuccessful in connecting to the database.

Variable:

- mod id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_db_connect().

Action Required: None. The program exits after issuing the message.

2312 E mod id: cl vol read failure: status = status

Explanation: An attempt to read a volume record from the database failed.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_vol_read().

Action Required: None. The program exits after issuing the message.

2313 E mod id: cl_cel_read failure: status = status

Explanation: An attempt to read a cell record from the database failed.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_cel_read().

Action Required: None. The program exits after issuing the message.

2314 E mod id: cl lsm read failure: status = status

Explanation: An attempt to read an LSM record from the database failed.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_lsm_read().

Action Required: None. The program exits after issuing the message.

2315 E mod_id: cl_drv_read failure: status = status

Explanation: An attempt to read a drive record from the database failed.

Variable:

- mod id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_drv_read().

Action Required: None. The program exits after issuing the message.

2316 E mod id: cl loc read failure: status = status

Explanation: An attempt to read a lock record from the database failed.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_loc_read().

Action Required: None. The program exits after issuing the message.

2317 E mod_id: cl_vac_read failure: status = status

Explanation: An attempt to read a volume access control record from the database failed.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_vac_read().

Action Required: None. The program exits after issuing the message.

2318 E mod id: cl vol destroy failure: status = status

Explanation: An attempt to delete a volume record from the database failed.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_vol_destroy().

Action Required: None. The program exits after issuing the message.

2319 E mod id: cl_cel_write failure: status = status

Explanation: An attempt to update a cell record on the database failed.

Variable:

- mod id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_cel_write().

Action Required: None. The program exits after issuing the message.

2320 E mod id: cl db disconnect failure: status = status

Explanation: An attempt to disconnect from the database failed.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_db_disconnect().

Action Required: None. The program exits after issuing the message.

2321 E mod id: Cartridge Recovery failure: status = status

Explanation: The Cartridge Recovery (ACSCR) component returned an error.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from the Cartridge Recovery component (ACSCR).

Action Required: None. The program exits after issuing the message.

2322 E mod id: cl ipc write failure: status = status

Explanation: The ipc write function returned an error.

Variable:

- mod_id is the name of the module issuing the error message.
- *status* is the text of the status value returned from cl_ipc_write().

Action Required: None. The program exits after issuing the message.

2323 E mod id: cl ipc read failure: status = status

Explanation: The ipc read function returned an error.

Variable:

- mod id is the name of the module issuing the error message.
- status is the text of the status value returned from cl_ipc_read().

Action Required: None. The program exits after issuing the message.

2324 E mod id: cl ipc destroy failure: status = status

Explanation: The cl ipc destroy function returned an error.

Variable:

- mod id is the name of the module issuing the error message.
- *status* is the text of the status value returned from the function.

Action Required: None.

2325 E mod id: cl qm init failure: status = status

Explanation: The cl qm init function returned an error.

Variable:

- mod id is the name of the module issuing the error message.
- status is the text of the status value returned from the function.

Action Required: None.

2326 E mod id: cl qm qcreate failure: queue = queue name

Explanation: The cl qm qcreate function returned an error.

Variable:

- *mod id* is the name of the module issuing the error message.
- queue name is the name of the internal queue for which the failure occurred.

Action Required: None.

2327 E mod_id: cl_qm_mcreate failure: queue = queue_name

Explanation: The cl qm mcreate function returned an error.

Variable:

- mod id is the name of the module issuing the error message.
- queue name is the name of the internal queue for which the failure occurred.

Action Required: None.

2328 E mod id: cl qm maccess failure: member = member id

Explanation: The cl qm maccess function returned an error.

Variable:

- mod id is the name of the module issuing the error message.
- member id is the identifier of the queue member for which the failure occurred.

Action Required: None.

2329 E mod_id: cl_qm_mlocate failure: member = member_id

Explanation: The cl qm mlocate function returned an error.

Variable:

- mod id is the name of the module issuing the error message.
- *member id* is the identifier of the queue member for which the failure occurred.

Action Required: None.

2330 E mod_id: cl_qm_mdelete failure: member = member_id

Explanation: The cl_qm_mdelete function returned an error.

Variable:

- mod_id is the name of the module issuing the error message.
- member id is the identifier of the queue member for which the failure occurred.

Action Required: None.

2331 I Unreadable label found in *location_type location_id*: logged as *vol id*

Explanation: In the course of performing Cartridge Recovery, a cartridge with an unreadable label was discovered. No cartridge with a virtual label was recorded in this location.

Variable:

- *location_type* is the type of location (cell, drive) in which the unreadable label was detected.
- *location_id* is the specific identifier of the location (*cell id* or *drive id*).
- *vol_id* is a generated volume identifier of the form UL@nnn where nnn begins with 001 when Cartridge Recovery is initialized and is incremented each time an unreadable cartridge is reported. If the location is a drive, this volume identifier is recorded in the drive record.

Action Required: The unreadable cartridge is not ejected by Cartridge Recovery. If the location is a drive, the cartridge will be processed during dismount. If the location is a cell, physical removal of the unreadable cartridge may be required. Audit can be used to check the cell and will result in ejection.

> 2332 I Duplicate label found in location type location id: label=vol id logged as dup id

> > **Explanation:** In the course of performing Cartridge Recovery, a cartridge was encountered which appears to be a duplicate. The cartridge was found unexpectedly while looking for some other cartridge, and when the recorded home cell for the unexpected cartridge was checked, the home cell contained what is presumed to be the original cartridge.

Variable:

- location type is the type of location (cell, drive) in which the unreadable label was detected.
- location id is the specific identifier of the location (cell id or drive id).
- vol id is the volume identifier of the cartridge for which a duplicate was found. If the encountered label was unreadable, this may be a virtual label.
- dup id is a generated volume identifier of the form DL@nnn where nnn begins with 001 when Cartridge Recovery is initialized and is incremented each time a duplicate cartridge is reported. If the location is a drive, this volume identifier is recorded in the drive record.

Action Required: The duplicate cartridge is not ejected by Cartridge Recovery. If the location is a drive, the cartridge will be processed during dismount. If the location is a cell, physical removal of the duplicate cartridge may be required.



Note that the eject command can not be used to remove the cartridge, since it would eject the original rather than the duplicate, and no record exists for the generated volume identifier.

> 2334 I Found volume vol id in location will check home cell id when 1sm lsm id comes online.

> > **Explanation:** In the course of performing Cartridge Recovery, a cartridge was encountered unexpectedly in a storage cell. When attempting to check the recorded home cell for that cartridge, the home LSM was found to be offline or inaccessible. The cartridge may be a duplicate, but that could not be determined at this time. The recorded home cell is marked as reserved, which will cause it to be checked when the LSM comes online. The volume record is updated to reflect the new location in which it was found.

Variable:

- *vol id* is the volume identifier of the cartridge.
- *location* is the location in which the cartridge was found.
- home cell id is the recorded home cell for the cartridge.
- lsm_id is the identifier of the LSM containing the recorded home cell.

Action Required: None. When the LSM containing the old home cell comes online, the cell will be checked and its status corrected.

> 2335 I Volume vol id missing, home cell was cell id, drive was drive id, unable to examine location

> > **Explanation:** This tape cartridge was not found where ACSLS expected it, but either the home cell or the drive couldn't be examined during the recovery process. The volume record will remain in the database with a missing status until ACSLS can examine all recorded locations.

Variable:

- *vol id* is the volume identifier of the missing cartridge.
- cell id is the home cell recorded for the cartridge.
- drive id is the drive recorded for the cartridge.
- location is the location (either cell, drive, or cell and drive) that ACSLS could not examine.

Action Required: At least one recorded location could not be examined. ACSLS will automatically attempt to recover the cartridge when an LSM comes online. The missing status will be resolved when:

- The cartridge is found in one of the recorded locations by Cartridge Recovery. The volume record will be updated to reflect the location of the cartridge.
- Cartridge Recovery is able to check all recorded locations, and the cartridge is not found. In this case, the volume record will be deleted.
- Manual Volume Delete is used to delete the volume record from the database.

2336 I Volume vol id was not found and will be deleted

Explanation: This tape cartridge was not found in any location recorded by ACSLS. The volume record will be deleted from the database. This message will be followed by a 1054 I message that specifies the home cell and drive id which were recorded for this volume.

Variable: *vol_id* is the volume identifier of the cartridge that will be deleted.

Action Required: None

. 2338 E mod id: Invalid volume id vol id

Explanation: This messages is issued when an invalid volume ID is entered.

Variable:

- mod_id is the name of the module issuing the error message.
- *vol id* is the identifier of the volume that was found.

Action Required: Reenter the command with the correct volume ID.

2339 E Volume *vol_id*: Media type mismatch, recorded as *media type*, read as *media type*.

Explanation: The media type of the specified volume is recorded differently in the database than what was returned from a physical catalog of the volume's location. This could possible indicate that a label has fallen off.

Variable:

- *vol_id* is the volume serial number found by Cartridge Recovery.
- *media type* is the jvolume's media type designator.

Action Required: Cartridge may need to be relabeled. Operator intervention may be necessary.

> **2340 E** surr_main (*PID #####*): Unable to set SO_REUSEADDR on SURROGATE LISTENER socket NNNNN

> > **Explanation:** The Surrogate main routine was unable to set the SO REUSEADDR option on the socket using the setsockopt() system call. This option allows the socket at that port number to be reused if it still exists as can be the case if ACSLS is restarted soon after it was stopped. IPC Surrogate terminates.

Variable:

- ##### is the Process ID of the Surrogate issuing the error.
- NNNNN is the port number that the Surrogate is trying to set the option on.

- 1. Look for associated errors that may indicate why the setsockopt call failed.
- 2. Kill the ACSLS system using the kill.acsls command,
- 3. Then kill any additional "zombie" ACSLS processes (using a ps | grep acs).
- 4. See if the socket is in use (possibly by another process) with a netstat -a | grep NNNNN where NNNNN is the socket number shown in the error message.
- 5. If the socket is in use, wait for a few minutes to see if the socket eventually times out. Then restart ACSLS with the rc.acsss command.



- It may be necessary to reboot the ACSLS host to release any hung sockets.
- 6. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2341 E surr_main (*PID #####*): Unable to bind SURROGATE LISTENER socket NNNNN

Explanation: The Surrogate main routine was unable to bind the main listener socket that it uses to accept requests from the Gateway on using the bind() system call. Each Surrogate has a unique port number it is trying to bind to. IPC Surrogate terminates.

Variable:

- #### is the Process ID of the Surrogate issuing the error.
- *NNNNN* is the port number that the Surrogate is trying to bind() to.

- Look for associated errors that may indicate why the bind()
 call failed.
- 2. Kill the ACSLS system using the kill.acsls command.
- 3. Then kill any additional "zombie" ACSLS processes (using a ps | grep acs).
- 4. See if the socket is in use (possibly by another process) with a netstat –a | grep NNNNN where NNNNN is the socket number shown in the error message.
- 5. If the socket is in use, wait for a few minutes to see if the socket eventually times out. Then restart ACSLS with the rc.acsss command.



- It may be necessary to reboot the ACSLS host to release any hung sockets.
- 6. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2342 E surr main (PID #####): Listen error on SURROGATE LISTENER socket NNNNN

Explanation: The Surrogate main routine was unable to complete a listen() system call on the main listener socket that it uses to accept requests from the Gateway. Each Surrogate has a unique port number it is trying to listen() to. IPC Surrogate terminates.

Variable:

- #### is the process ID of the Surrogate issuing the error.
- NNNNN is the port number that the Surrogate is trying to listen() to.

- 1. Look for associated errors that may indicate why the listen() call failed.
- 2. Kill the ACSLS system using the kill.acsls command.
- 3. Then kill any additional "zombie" ACSLS processes (using a ps | grep acs).
- 4. See if the socket is in use (possibly by another process) with a netstat –a | grep NNNNN where NNNNN is the socket number shown in the error message.
- 5. If the socket is in use, wait for a few minutes to see if the socket eventually times out. Then restart ACSLS with the rc.acsss command.



- It may be necessary to reboot the ACSLS host to release any hung sockets.
- 6. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2343 I PID ##### surr_main (PID #####): Surrogate listening on port

NNNNNN SURROGATE_QUEUE_AGE is set to NNN minutes

SURROGATE_TIMEOUT is set to NNN seconds TRACING is

<ON/OFF> QUEUE currently has NN active requests

Explanation: This message indicates what socket port the Surrogate is listening on to receive ACSLS requests from a Library Management Gateway system. It is issued when the Surrogate starts and has successfully created, bound, and is actively listening on the socket. Also shown are the current values that the program is using for SURROGATE_QUEUE_AGE and SURROGATE_TIMEOUT. These two variables and the SURROGATE_PORT are dynamic environment variables set in the acsss_config program. Also displayed is whether program tracing is set "on" or "off". Finally, the number of requests that are currently on the queue is shown. This message is also displayed when the program receives a SIGHUP signal (i.e., kill -hup #####). The Surrogate continues running.

Variable:

- ##### is the Process ID of the Surrogate issuing the message.
- *NNNNN* is the number of the port on which the Surrogate is listening.
- NN is the number of minutes that SURROGATE_QUEUE_AGE is set to.
- NNN is the number of seconds until SURROGATE_TIMEOUT. takes effect.
- *NN* is the number of active requests in the **QUEUE**

Action Required: None. This message is informational only.

> 2344 E surr main (PID ####): Socket initialization failed for SURROGATE LISTENER socket NNNNN; rc=XX

> > **Explanation:** The Surrogate main routine was unable to complete a listen() system call on the main listener socket that it uses to accept requests from the Library Management Gateway. Each Surrogate has a unique port number it is trying to listen() to. IPC Surrogate terminates.

Variable:

- #### is the Process ID of the Surrogate issuing the error.
- NNNNN is the port number that the Surrogate is trying to listen() to.
- XX is the return code from the listen() call.

Action Required:

- 1. Look for associated errors that may indicate why the listen() call failed.
- 2. Kill the ACSLS system using the kill.acsls command.
- 3. Then kill any additional "zombie" ACSLS processes (using a ps | grep acs).
- 4. See if the socket is in use (possibly by another process) with a netstat $-a \mid grep NNNNN$ where NNNNN is the socket number shown in the error message.
- 5. If the socket is in use, wait for a few minutes to see if the socket eventually times out. Then restart ACSLS with the rc.acsss command.



Hint: It may be necessary to reboot the ACSLS host to release any hung sockets.

6. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2345 W surr_handler (PID #####): Due to above error, packet is dropped & GATEWAY CONNECTED socket (NNNNN) closed

Explanation: The Surrogate handler routine encountered an error earlier, which rendered the current ACSLS request unable to run to completion. Consequently, the Surrogate is forced to abort that particular request packet and close the socket that it was using to communicate with the Library Management Gateway servlet (the GATEWAY CONNECTED socket). This error is not considered fatal to the Surrogate. PC Surrogate closes the socket, removes the queue entry, and continues running.

Variable:

- #### is the process ID of the Surrogate issuing the error.
- *NNNNN* is the socket number that the Surrogate has closed.

- 1. Look for an error message preceding this one that caused the packet to be dropped and socket closed.
- 2. Look for other associated errors on the Gateway, Adapter, and client machines.
- 3. Try to identify the ACSLS command that is being sent from the originating client system.
- 4. If possible, re—send the offending command with tracing turned on for the Surrogate, Gateway, and Adapter.
- 5. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

> 2346 E surr_handler (PID #####): Write of ipc data to GATEWAY CONNECTED socket NNNNN failed

> > **Explanation:** The Surrogate handler routine encountered an error trying to write data to the socket connected to the Library Management Gateway servlet (GATEWAY CONNECTED socket). The write() system call failed. This may have occurred because the socket prematurely closed before all the data was written. IPC Surrogate terminates.

Variable:

- #### is the process ID of the Surrogate issuing the error.
- NNNNN is the socket number that the Surrogate was trying to write to.

Action Required: This could be a possible hardware or network failure.

- 1. Look for associated error messages preceding this one that may indicate the cause.
- 2. Look for other associated errors on the Gateway, Adapter, and client machines.
- 3. Try to identify the ACSLS command that was being sent from the originating client system.
- 4. If possible, re–send the offending command with tracing turned on for the Surrogate, Gateway, and Adapter.
- 5. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

> 2347 E surr handler (PID #####): Wrote XX rather than YY bytes of data to GATEWAY CONNECTED socket NNNNN

> > **Explanation:** The Surrogate handler routine encountered an error trying to write data to the socket connected to the Library Management Gateway servlet (GATEWAY CONNECTED socket). The write() system call could not write the expected number of bytes to the socket. This may be due to the socket's prematurely closing. IPC Surrogate terminates.

Variable:

- #### is the Process ID of the Surrogate issuing the error.
- XX is the number of bytes returned by the write() system call.
- YY is the number of bytes the Surrogate program attempted to write to the socket.
- NNNNN is the socket number that the Surrogate was trying to write to.

Action Required: This could be a possible hardware or network failure.

- 1. Look for associated error messages preceding this one that may indicate the cause.
- 2. Look for other associated errors on the Gateway, Adapter, and client machines.
- 3. Try to identify the ACSLS command that was being sent from the originating client system.
- 4. If possible, re–send the offending command with tracing turned on for the Surrogate, Gateway, and Adapter.
- 5. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

> 2348 E surr handler (PID #####): Unable to create a GATEWAY CONNECTED socket via ACCEPT (SURROGATE LISTENER NNNNN)

> > **Explanation:** The Surrogate handler routine was unable to complete an accept() system call on the main listener socket that it uses to accept requests from a Gateway servlet. Each Surrogate has a unique port number it is trying to listen() to. A new socket connection for the Gateway servlet is created as a result of a successful accept() call known as a GATEWAY CONNECTED socket. IPC Surrogate terminates.

Variable:

- ##### is the Process ID of the Surrogate issuing the error.
- NNNNN is the port number that the Surrogate is trying to listen() to.

- 1. Look for associated errors that may indicate why the accept() call failed.
- 2. Kill the ACSLS system using the kill.acsls command.
- 3. Then kill any additional "zombie" ACSLS processes (using a ps | grep acs and kill –9 the appropriate ids.
- 4. See if the socket is in use (possibly by another process) with a netstat $-a \mid grep NNNNN$ where NNNNN is the socket number shown in the error message.
- 5. If the socket is in use, wait for a few minutes to see if the socket eventually times out. Then restart ACSLS with the rc.acsss command.



- It may be necessary to reboot the ACSLS host to release any hung sockets.
- 6. Also look for exceeding UNIX system limits on sockets, file descriptors, or other network resources.
- 7. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1

Messages manual). Then contact StorageTek Software Support.

2349 E surr_read_socket (*PID #####*): "Read failed on GATEWAY CONNECTED socket *NNNNN*

Explanation: The Surrogate read socket routine was unable to complete an read() system call on the socket that it uses to accept requests from a Library Management Gateway servlet. Each Surrogate has a unique port number it is trying to listen() to. A new socket connection for the Gateway servlet is created as a result of a successful accept() call known as a GATEWAY CONNECTED socket. The GATEWAY CONNECTED socket is closed and the IPC Surrogate continues running.

Variable:

- ##### is the process ID of the Surrogate issuing the error.
- *NNNNN* is the port number that the Surrogate is trying to read() from.

Action Required:

- Look for associated errors that may indicate why the read() call failed.
- 2. Kill the ACSLS system using the kill.acsls command.
- 3. Then kill any additional "zombie" ACSLS processes (using a ps | grep acs and kill –9 the appropriate ids).
- 4. See if the socket is in use (possibly by another process) with a netstat –a | grep NNNNN where NNNNN is the socket number shown in the error message.
- 5. If the socket is in use, wait for a few minutes to see if the socket eventually times out. Then restart ACSLS with the rc.acsss command.

Note: It may be necessary to reboot the ACSLS host to release any hung sockets. This may be a result of a timeout of the command and increasing network timeout parameters may alleviate the condition.

> 6. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2350 E surr read socket (PID ####): "Read X bytes from GATEWAY CONNECTED socket (NNNNN) but expected Y

> **Explanation:** The Surrogate read socket routine was unable to complete an read() system call on the socket that it uses to accept requests from a Library Management Gateway servlet. Each Surrogate has a unique port number it is trying to listen() to. A new socket connection for the Gateway servlet is created as a result of a successful accept() call known as a GATEWAY CONNECTED socket. It was trying to read Y number of bytes but only read X number of bytes. Surrogate continues running.

Variable:

- #### is the Process ID of the Surrogate issuing the error.
- NNNNN is the port number that the Surrogate is trying to read() from.
- X is the number of bytes that were successfully read.
- Y is the number of bytes that it was trying to read.

- 1. Look for associated errors that may indicate why the read() call failed.
- 2. Kill the ACSLS system using the kill.acsls command.
- 3. Then kill any additional "zombie" ACSLS processes (using a ps | grep acs and kill –9 the appropriate ids).
- 4. See if the socket is in use (possibly by another process) with a netstat $-a \mid grep NNNNN$ where NNNNN is the socket number shown in the error message.

> 5. If the socket is in use, wait for a few minutes to see if the socket eventually times out. Then restart ACSLS with the rc.acsss command.

Note: It may be necessary to reboot the ACSLS host to release any hung sockets. This may be a result of a timeout of the command and increasing network timeout parameters may alleviate the condition.

6. If this does not solve the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2351 E surr handler (PID #####): select() call failed on GATEWAY CONNECTED socket (NNNNN)

> **Explanation:** The Surrogate handler routine failed on a select() system call. This routine blocks on the socket that it uses to accept requests from a Library Management Gateway servlet and on the socket it uses to communicate with the acslm process. Each Surrogate has a unique port number it is trying to listen() to. A new socket connection for the Library Management Gateway servlet is created as a result of a successful accept() call known as a GATEWAY CONNECTED socket. IPC Surrogate terminates.

Variable:

- ##### is the Process ID of the Surrogate issuing the error.
- NNNNN is the port number for the Gateway connected to the Surrogate.

- 1. Look for associated errors that may indicate why the select() call failed.
- 2. See if the acslm process failed.
- 3. Check for the Gateway port by looking for it with the netstat –a | grep NNNNN.

4. Kill the ACSLS system using the kill.acsls command.

- 5. Then kill any additional "zombie" ACSLS processes (using a ps | grep acs and kill –9 the appropriate ids.
- 6. See if the socket is in use (possibly by another process) with a netstat $-a \mid grep NNNNN$ where NNNNN is the socket number shown in the error message.
- 7. If the socket is in use, wait for a few minutes to see if the socket eventually times out. Then restart ACSLS with the rc.acsss command.

Note: It may be necessary to reboot the ACSLS host to release any hung sockets.

- 8. Also look for exceeding UNIX system limits on sockets, file descriptors, or other network resources.
- 9. If this does not solve the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

> 2352 W surr handler (PID #####): COMMAND (ACK | INTERMEDIATE | FINAL) response discarded because original socket connection is no longer on the queue. Advise increasing SURROGATE QUEUE AGE.

> > **Explanation:** The ACSLS library manager returned a response to the Surrogate handler routine for the COMMAND shown, but the Surrogate could not find the outstanding request and socket connection on its queue, so its only alternative was to report the problem and discard (ignore) the response from the library manager. This may result from the library's taking too long to execute commands. For example, a mount or dismount may be taking an exceedingly long time because of hardware errors, a drive being cleaned before mounting, cartridges too far from the requested drive (i.e., different LSM), or other conditions. After a few minutes have passed (SURROGATE QUEUE AGE), the request on the queue is considered "stale" and removed from the queue. Eventually, when the library finally mounts or dismounts the tape, the FINAL response packet from the library manager can no longer be found on the queue and transmitted to the client. The Surrogate continues running.

Variable:

- COMMAND is the ACS command for which the Surrogate could not find an outstanding request and socket connection.
- SURROGATE QUEUE AGE is the dynamic environment variable that controls how long the Surrogate keeps requests on its queue.

- 1. Look for any unusual conditions that may cause ACS commands to be delayed (see the explanation above).
- 2. Determine if the hardware is malfunctioning or misconfigured.
- 3. To increase the amount of time that the Surrogate keeps requests on its queue, increase the SURROGATE QUEUE AGE

> dynamic environment variable with the acsss_config program.

4. Restart the Surrogate to enable the change to take effect.

2353 E surr_query_server (PID ####): Surrogate process unable to issue query server (NN seconds)

> **Explanation:** The Surrogate issues a "Query Server" request to the library manager when it starts running to be sure the library manager is ready to receive requests and before the Surrogate begins accepting requests from the Library Management Gateway socket. The Surrogate is expecting the server to be in RUN or RECOVERY mode. After waiting the number of seconds shown, the Surrogate determined that the "Query Server" could not be completed and gave up. The Surrogate abnormally terminates and is automatically restarted (up to 10 times) by the acsss daemon.

Variable:

- #### is the Process ID of the Surrogate issuing the error.
- NN is the number of seconds

- 1. Look for errors in the acsss_event.log that may explain why a "query server" request cannot be completed.
- 2. Try the "Query Server" request in cmd_proc.

2354 W surr_query_server (PID ####): Surrogate waiting for ACSLS to come up

Explanation: The Surrogate issues a "Query Server" request to the library manager when it starts running to be sure the library manager is ready to receive requests and before the Surrogate opens the Library Management Gateway listening socket to begin accepting requests. The Surrogate is expecting the server to be in RUN or RECOVERY mode. The Surrogate will issue this message every 30 seconds (for up to 10 minutes) till a "Query Server" returns that it is in RUN or RECOVERY mode. Once it is in RUN or RECOVERY mode, the Surrogate will continue coming up. If 10 minutes passes, then the surrogate will abnormally terminate with error 2353.

Note that this can occur if the system starts up in IDLE mode.

Variable: ##### is the Process ID of the Surrogate issuing the error.

- 1. Look for errors in the acsss_event.log that may explain why a query server isn't in RUN or RECOVERY mode.
- 2. Try the query server request in cmd_proc.
- 3. Check to see if ACSLS is set to automatically start in IDLE mode using the acsss config program.
- 4. If the system is in IDLE mode, issue a START command.

> **2355 E** "ss main: Too many SURROGATE processes specified through acsss config. The maximum is 10 SURROGATE processes

> > **Explanation:** The acsss_daemon read the SURROGATE PROCESSES dynamic environment variable in order to know how many surrogate processes to start. The number exceeds ten (10), the maximum allowed. ACSLS terminates.

Variable: SURROGATE PROCESSES is the dynamic environment variable that controls the number of surrogate processes running.

Action Required: The range for the dynamic environment variable SURROGATE PROCESSES has been set greater than the Surrogate program currently supports. Define the SURROGATE PROCESSES variable with the acsss config program to be a number less than 10.

2356 W surr handler (PID #####): NN surrogate requests (open socket) being processed; cannot accept more until some finish. Advise reducing SURROGATE QUEUE AGE.

> **Explanation:** The surrogate handler routine was unable to complete an accept() system call on the main listener socket that it uses to accept requests from a Library Management Gateway servlet. Each SURROGATE has a unique port number it is trying to listen() to. A successful accept() call (known as a GATEWAY CONNECTED socket) creates a new socket connection for the Gateway servlet. The error code (errno) and message returned by the accept() system call is "24 - TOO MANY OPEN FILES".

The SURROGATE will disregard the Library Management Gateway's attempt to connect its servlet to a SURROGATE socket. As requests are completed and open socket connections are closed, future attempts to connect will complete successfully. The SURROGATE will not abort on this error. Since it is possible for the Library Management Gateway to continue connection

> attempts (and fill the acsss_event.log), this error message will be displayed in the acsss_event.log no more often than every five (5) minutes. The SURROGATE continues running.

Variable:

- ##### is the process ID of the SURROGATE issuing the error.
- NN is the number of open sockets.
- SURROGATE QUEUE AGE is the dynamic environment variable that controls the length of time a request remains in the queue.

Action Required: Generally the problem is that the Library Management Gateway has sent more requests than the ACSLS system can process (or has sent them too fast) or that the ACSLS library system is processing the requests too slowly. Thus, the SURROGATE has reached the maximum limit of open files (sockets).

- 1. Look for errors in the acsss_event.log that may show indicate hardware or configuration errors.
- 2. Also try a query request all command in cmd proc to see how many requests ACSLS are outstanding.
- 3. Check client software to see if many mount and dismount requests are being sent.
- 4. It may also be necessary to reduce the amount of time that the SURROGATE keeps outstanding requests on its queue. Reduce the SURROGATE QUEUE AGE dynamic environment variable with the acsss config program.
- 5. Restart the SURROGATE so that the change can take effect.

> 2361 N Volume vol id: Media type incompatible with L5500. Not entered.

> > **Explanation:** This message pertains to L5500 LSMs only; it indicates an attempt to enter an incompatible cartridge into an L5500 CAP. Only LTO and StorageTek 9840/9940 cartridges are compatible with L5500 LSMs. Requests to enter incompatible media are rejected.

Variable: *vol id* is the volume entered into the CAP.

Action Required:

- Remove the cartridge from the CAP.
- Substitute an LTO or StorageTek 9840/9940 cartridge.

2362 N Cell *cell id* contains incompatible media: must be manually removed

> **Explanation:** This message pertains to L5500 LSMs only. The message indicates that an audit found a cartridge that is neither an LTO cartridge nor a StorageTek 9840 or 9940 cartridge in an L5500 panel. Only LTO and StorageTek 9840/9940 cartridges are compatible with L5500 LSMs. (This may have been caused by someone physically entering the LSM and manually placing the cartridge in the panel.)

Variable: cell id is the cell in the L5500 containing the incompatible cartridge.

Action Required: Physically enter the L5500 and manually remove the incompatible cartridge.

> 2363 E Request emergency software license key from the StorageTek web site. Go to Customer Resource Center, Tools and Services, Emergency Software Key.

> > **Explanation:** Software license key validation has failed due to an invalid or nonexistent key, an expired key, or because the cartridge count exceeded the library's licensed capacity.

Action Required: Follow the directions in the message to obtain an emergency software key. Contact your sales account representative to obtain a valid periodic software license key.

Note: This may result in additional charges if the software license has expired or if the cartridge count exceeds the library's current licensed capacity.

2400 E EXEC SQL select failed on table table name.

Explanation: An ODBC call to prepare an SQL statement for selecting records from table table name has failed.

Variable: table name is the name of the table from which the records were to be selected.

- Restart the application server.
- If the problem persists, restart the database.
- If the problem persists, contact your System Administrator.

2401 E XML Error (error message) with error code (code).

Explanation: An XML Exception has occurred.

Variable:

- *error message* is the XML Exception message.
- *code* is the error code from the XML Exception.

Action Required:

• Check the validity of the XML in the Request.

2402 E XML Parsing Error (error message).

Explanation: An SAX Exception has occurred in parsing the XML.

Variable: *error message* is the SAX Exception message.

Action Required: Check the validity of the XML in the Request.

2403 E Invalid DISPLAY type detected.

Explanation: The type in the display response packet is

invalid.

Variable: None. **Action Required:**

- Retain the request XML and the response from the display processor.
- Contact StorageTek Software Support.

2404 I Display tables could not be loaded.

Explanation: The display reference talbes could not be loaded into the database during configuration.

Variable: None.

Action Required:

- Restart the database.
- If the problem persists, contact your System Administrator.

2405 E EXEC SQL Cannot create database handle

Explanation: An ODBC call to create a handle to query the database has failed.

Variable: None.

Action Required:

- Restart the application server.
- If the problem persists, restart the database.
- If the problem persists, contact your System Administrator.

2406 E EXEC SQL Cannot register variables

Explanation: An ODBC call to specify the variables to store the records from the database has failed.

Variable: None.

Action Required:

- Restart the application server.
- If the problem persists, restart the database.
- If the problem persists, contact your System Administrator.

2407 E Unexpected XML parsing error occurred

Explanation: An unexpected parsing error occurred in the

XMI.4c APIs.

Variable: None. **Action Required:**

• Restart the application server.

- If the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.
- If the problem persists, contact your System Administrator.

2408 I acsdisp failed, database query string too long.

Explanation: The database query is too long to be passed

through ODBC to query the database.

Variable: None.

Action Required: Please enter a shorter query.

2420 E EXEC SQL failed to fetch from cursor.

Explanation: An ODBC call to prepare an SQL statement for fetching a row from the database with the *cursor* has failed.

Variable: cursor is the database handle for executing SQL

statement.

Action Required: The application server has to be re–started.

Contact your System Administrator.

2421 W DB status $[err_num]$ detected on update for client id client id

Explanation: An attempt to update a client record in the database has failed.

Variable:

- err num is the error number.
- *client id* is the identifier of the client to be deleted.

Action Required:

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2422 W DB status $[err_num]$ detected on insert for client id $clnt_id$

Explanation: An attempt to insert a client record into the database has failed.

Variable:

- *err num* is the error number.
- *clnt id* is the identifier of the client to be deleted.

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of

> this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2423 E EXEC SQL failed to insert client id clnt id into clienttable

> **Explanation:** An ODBC call to prepare an SQL statement for inserting a client record into the database has failed.

Variable: *clnt id* is the identifier of the client to be deleted.

Action Required:

- Restart the application server and see if the problem
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2424 E EXEC SQL lock timeout on update of clienttable where client id = clnt id

> **Explanation:** An attempt to update a locked client record from clienttable has failed.

Variable: *clnt id* is the identifier of the client to be deleted.

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2425 E EXEC SQL failed to update clienttable where client_id = clnt id

Explanation: An ODBC call to prepare an SQL statement for updating a client record has failed.

Variable: *clnt id* is the identifier of the client to be deleted.

Action Required:

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2426 E DB status $[err_num]$ detected on operation for lib_cmpnt $cmpnt_id$

Explanation: An attempt to perform a database operation like the insertion, deletion or updating of a library component *lib_cmpnt*, e.g., LMU or PTP or HAND or PANEL with an identifier *cmpnt_id*, e.g., 0,0(lmu_id) or 0,0,0(panel_id or ptp_id) or 0,0,0,0(hand_id), has failed.

Variable:

- err num is the error number.
- *lib_cmpnt* is the library component type, e.g., LMU, PTP, HAND or PANEL.
- cmpnt_id is the identifier of a library component, e.g., 0,0(lmu_id) or 0,0,0(ptp_id or panel_id) or 0,0,0,0(hand_id).

Action Required:

• Restart the application server and see if the problem persists.

> • If it does, restart the database and see if the problem persists.

• If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2427 E EXEC SQL lock timeout on delete from table name where lib cmpnt = cmpnt id

> **Explanation:** An attempt to delete a locked a record from the table name, e.g., lmutable, ptptable or handtable for a library component lib cmpnt, e.g., LMU, PTP or HAND with an identifier *cmpnt* id, e.g., 0,0(lmu_id) or 0,0,0(ptp_id) or 0,0,0,0(hand id), has failed.

Variable:

- table name is the name of the database table from which row has to be deleted.
- lib cmpnt is library component type, e.g., LMU, PTP or HAND.
- cmpnt id is the identifier of the library component, e.g., 0,0(lmu_id) or 0,0,0(ptp_id) or 0,0,0,0(hand_id).

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

> 2428 E EXEC SQL delete from table name failed, where lib cmpnt = cmpnt id

> > **Explanation:** An ODBC call to prepare an SQL statement for deleting a record from the table name, e.g., lmutable, ptptable or handtable for a library component, e.g., LMU, PTP or HAND with an identifier *cmpnt* id, e.g., 0,0(lmu_id) or 0,0,0(ptp_id) or 0,0,0,0(hand_id), has failed.

Variable:

- table name is the name of the database table from which row has to be deleted.
- *lib cmpnt* is library component type, e.g., LMU, PTP or HAND.
- cmpnt id is the identifier of a library component, e.g., 0,0(lmu_id) or 0,0,0(ptp_id) or 0,0,0,0(hand_id).

Action Required:

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2429 E EXEC SQL select from table name failed, where lib cmpnt = cmpnt id

> **Explanation:** An ODBC call to prepare an SQL statement for selecting a record from the table name, e.g., lmutable, ptptable or handtable for a library component, e.g., LMU, PTP or HAND with an identifier *cmpnt* id, e.g., 0,0(lmu_id) or 0,0,0(ptp_id) or 0,0,0,0(hand id), has failed.

Variable:

> table name is the name of the database table from which row has to be deleted.

- lib cmpnt is library component type, e.g., LMU, PTP or HAND.
- cmpnt id is the identifier of a library component, e.g., 0,0(lmu id) or 0,0,0(ptp id) or 0,0,0,0(hand id).

Action Required:

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2430 E Table table name loading failed.

Explanation: ACSLS loads Access Control data files to temporary database tables before rebuilding the Access Control database tables. This message indicates that an attempt to load an Access Control data file to the specified temporary Access Control database table has failed.

Variable: table name is the name of the Access Control temporary database table.

- If ACSLS is running, execute acsss config as user "acsss" and select the option to rebuild the Access Control tables.
- If ACSLS is not running, execute rc.acsss as user "acsss".
- If the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on

page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2431 E Table *table name* rebuilding failed.

Explanation: To ensure that the Access Control database tables are locked while they are rebuilt, ACSLS loads Access Control data files to temporary database tables and uses the temporary tables to rebuild the Access Control database tables. This message indicates that an attempt to rebuild a specified Access Control database table has failed.

Variable: *table_name* is the name of the Access Control database table that ACSLS failed to rebuild.

Action Required:

- If ACSLS is running, execute acsss_config as user "acsss" and select the option to rebuild the Access Control tables.
- If ACSLS is not running, execute rc.acsss as user "acsss".
- If the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2432 I Access Control tables have been rebuilt.

Explanation: ACSLS has successfully rebuilt the Access Control tables.

Control tables.

Variable: None.

Action Required: None. This message is informational only.

> 2440 E EXEC SQL lock timeout: on insert into table name, where identifier = id

> > **Explanation:** An attempt to insert a record into the locked table table name, e.g., clienttable, lmutable, ptptable, paneltable or handtable, where identifier identifier, e.g., client_id, lmu_id, ptp_id, panel_id or hand_id with a value of id e.g., client1 (client_id) or 0,0(lmu_id) or 0,0,0(ptp_id or panel_id) or 0,0,0,0(hand_id), has failed.

Variable:

- table name is the name of the database table from which row has to be deleted.
- identifier is an identifier, e.g., client_id, lmu_id, ptp_id, panel_id or hand_id.
- id is the value of an identifier, e.g., client1(client_id), 0,0(lmu_id) or 0,0,0(ptp_id or panel_id) or 0,0,0,0(hand_id).

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

> 2441 E EXEC SQL failed lock to insert into table name, where identifier = id

> > **Explanation:** An ODBC call to prepare an SQL statement to insert a record into table table name, e.g., lmutable, ptptable, paneltable or handtable, where identifier identifier, e.g., lmu_id, ptp_id, panel_id or hand_id with a value of id, e.g., 0,0(lmu_id) or 0,0,0(ptp_id or panel_id) or 0,0,0,0(hand_id), has failed.

Variable:

- table name is the name of the database table from which row has to be deleted.
- identifier is an identifier, e.g., lmu id, ptp id, panel id or hand id.
- *id* is the value of an identifier, e.g., 0,0(lmu_id) or 0,0,0(ptp_id or panel_id) or 0,0,0,0(hand_id).

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.contact StorageTek Software Support. For more information, see Requesting Help from Software Support.

> 2442 E EXEC SQL lock timeout: on update table name, where identifier = id

> > **Explanation:** An attempt to update a record in the database for a locked table table name, e.g., Imutable, ptptable, paneltable or handtable, where identifier identifier, e.g., Imu_id, ptp_id, panel_id or hand_id with a value of id, e.g., 0,0(lmu_id) or 0,0,0(ptp_id or panel_id) or 0,0,0,0(hand_id), has failed.

Variable:

- table name is the name of the database table from which row has to be deleted.
- identifier is an identifier, e.g., lmu_id, ptp_id, panel_id or hand id.
- id is the value of an identifier, e.g., 0,0(lmu_id) or 0,0,0(ptp_id) or panel_id) or 0,0,0,0(hand_id).

Action Required:

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2443 E EXEC SQL update of table name failed, where identifier = id

Explanation: An ODBC call to prepare an SQL statement for updating a record in the database for the table table name, e.g., lmutable, ptptable, paneltable or handtable, where identifier identifier, e.g., lmu_id, ptp_id, panel_id or hand_id with a value of id, e.g., 0,0(lmu_id) or 0,0,0(ptp_id or panel_id) or 0,0,0,0(hand_id), has failed.

Variable:

> • table name is the name of the database table from which a row has to be deleted.

- identifier is an identifier, e.g., lmu_id, ptp_id, panel_id or hand id.
- *id* is the value of an identifier, e.g., 0,0(lmu_id) or 0,0,0(ptp id or panel id) or 0,0,0,0(hand id).

Action Required:

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2444 E EXEC SQL fetch from handtable failed

Explanation: An ODBC call to prepare an SQL statement for fetching a record from handtable has failed.

- Restart the application server and see if the problem persists.
- If it does, restart the database and see if the problem persists.
- If it does, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2445 E PTP *ptp id*, configuration failed to verify

Explanation: ACSLS has discovered a mismatch between hardware and the database during recovery. PTP information needs to be added to or deleted from the database.

Variable: The PTP identifier is *ptp id*.

Action Required: After recovery processing terminates, rerun the library server acsss config program to redefine the library configuration in the database (see the Installation and Configuration Guide for your platform).

2446 E Hand hand id, configuration failed to verify

Explanation: ACSLS has discovered a mismatch between hardware and the database during recovery. Hand information needs to be added to or deleted from the database.

Variable: The HAND identifier is *hand id*.

Action Required: After recovery processing terminates rerun the library server acsss config program to redefine the library configuration in the database (see the Installation and Configuration Guide for your platform).

2447 I lib cmpnt cmpnt id is operative.

Variable:

- *lib cmpnt* is the library component type, e.g., PTP, HAND, DRIVE or CAP.
- cmpnt id is the identifier of a library component, e.g., 0,0,0(ptp_id) or 0,0,0,0(hand_id) or 0,0,0(cap_id) or 0,0,7,1(drive id).

2448 W *lib_cmpnt cmpnt_id* is inoperative.

Explanation: This message is issued when the library component *lib_cmpnt*, e.g., PTP, HAND, DRIVE or CAP, with an identifier *cmpnt_id*, e.g., 0,0,0(ptp_id) or 0,0,0(hand_id) or 0,0,0(cap_id) or 0,0,7,1(drive_id), becomes inoperative.

Variable:

- lib_cmpnt is the library component type, e.g., PTP, HAND, DRIVE or CAP.
- *cmpnt_id* is the identifier of a library component, e.g., 0,0,0(ptp_id) or 0,0,0(hand_id) or 0,0,0(cap_id) or 0,0,7,1(drive_id).

Action Required: None.

2449 I CAP cap id CAP door closed.

Explanation: This message is issued when the door of CAP with value *cap id* is closed.

Variable: cap_id is the CAP whose access door is closed.

Action Required: None. This message is informational only.

2450 I lib cmpnt cmpnt id serial number changed.

Explanation: This message indicates that there is a change in serial number for a library component, e.g., LSM or drive, with an identifier *cmpnt id*, e.g., 0,0(lsm_id) or 0,0,7,1(drive_id).

Variable:

- lib_cmpnt is the library component type, e.g., LSM or DRIVE.
- *cmpnt_id* is the identifier of a library component, e.g., 0,0(lsm_id) or 0,0,7,1(drive_id).

2451 I Drive drive id type changed.

Explanation: The type is changed for the DRIVE identifier

with the value drive id.

Variable: *Drive* id is the value of the DRIVE identifier.

Action Required: None. This message is informational only.

2452 I LMU lmu id type changed.

Explanation: The type is changed for the LMU identifier with the value *lmu id*.

Variable: *lmu* id is the value of the LMU identifier.

Action Required: None. This message is informational only.

2453 I LSM *lsm id* type changed.

Explanation: The type is changed for the LSM identifier with the value *lsm id*.

Variable: *lsm id* is the value of LSM identifier.

Action Required: None. This message is informational only.

2454 I *lib_cmpnt cmpnt_id* added.

Explanation: A library component, e.g., DRIVE, with an identifier *cmpnt* id, e.g., 0,0,7,1(drive_id), has been added to the database.

Variable:

- *lib_cmpnt* is the library component type, e.g., DRIVE.
- cmpnt id is the identifier of a library component, e.g., 0,0,7,1(drive_id).

2455 I lib cmpnt cmpnt id removed.

Explanation: A library component, e.g., DRIVE, with an identifier *cmpnt id*, e.g., 0,0,7,1(drive_id), has been removed.

Variable:

- *lib cmpnt* is the library component type, e.g., DRIVE.
- *cmpnt_id* is the identifier of a library component, e.g., 0,0,7,1(drive_id).

Action Required: None. This message is informational only.

2456 W lib cmpnt cmpnt id maintenance required.

Explanation: A library component, e.g., LSM, with an identifier *cmpnt id*, e.g., 0,0(lsm_id) is in maintenance mode.

Variable:

- *lib cmpnt* is the library component type, e.g., LSM.
- *cmpnt_id* is the identifier of a library component, e.g., 0,0(lsm_id).

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2457 I *lib cmpnt cmpnt id* HLI Compatibility Level changed.

Explanation: The HLI compatibility level has changed for a library component, e.g., ACS or LMU with an identifier *cmpnt id*, e.g., 0(acs_id) or 0,0(lmu_id).

Variable:

- *lib_cmpnt* is the library component type, e.g., ACS or LMU.
- *cmpnt_id* is the identifier of a library component, e.g., acs_id or lmu_id.

2458 I LMU *lmu id* is now standalone.

Explanation: The status of LMU with value *lmu_id* is that of a standalone LMU.

Variable: *lmu id* is the value of the LMU identifier.

Action Required: None. This message is informational only.

2459 I LMU *lmu_id* is now master.

Explanation: The status of LMU with value *lmu_id* is that of the master LMU.

Variable: *lmu_id* is the value of LMU identifier.

Action Required: None. This message is informational only.

2460 I LMU *lmu id* is now standby.

Explanation: The status of the LMU with the value *lmu_id* is that of the standby LMU.

Variable: *lmu id* is the value of LMU identifier.

Action Required: None. This message is informational only.

2461 I Server system configuration changed.

Explanation: This message is issued when the server system configuration is changed.

Action Required: None. This message is informational only.

2462 I Volume vol id entered.

Explanation: This message is issued when VOLUME with value *vol id* is entered into the library.

Variable: *vol_id* is the VOLUME identifier.

2463 I Volume vol id reactivated.

Explanation: This message is issued when VOLUME with value *vol id* that was absent is reactivated.

Variable: *vol id* is the VOLUME identifier.

Action Required: None. This message is informational only.

2464 I Volume vol id ejected.

Explanation: This message is issued when VOLUME with value *vol id* is ejected from the library.

Variable: *vol id* is the VOLUME identifier.

Action Required: None. This message is informational only.

2465 I Volume vol id absent.

Explanation: This message is issued when VOLUME with value *vol id* is marked absent.

Variable: *vol id* is the VOLUME identifier.

Action Required: None. This message is informational only.

2466 W Cleaning cartridge *vol id* usage limit exceeded.

Explanation: A cleaning cartridge with the value *vol_id* has exceeded its maximum usage limit.

Variable: *vol id* is the VOLUME identifier.

Action Required: None. This message is informational only.

2467 I Cleaning cartridge *vol_id* is spent.

Explanation: The cleaning capacity of the cleaning cartridge with the value *vol id* is spent.

Variable: *vol id* is the VOLUME identifier.

2468 E *lib cmpnt cmpnt id* reported a Unit Attention.

Explanation: An LSM reported a Unit Attention status. This message is from the Event Notification component. Look for a preceding message from ACSLH scsilh that reports the specific Unit Attention status. The library is still operational after a Unit Attention Status is reported, but it may be in a degraded mode.

Variable:

- lib cmpnt is library component type, e.g., LSM, DRIVE or CAP.
- cmpnt id is the identifier of a library component, e.g., lsm_id, cap_id or drive_id.

Action Required:

- 1. Review the specific status reported earlier and respond to the problem reported. This may require calling StorageTek Hardware Support.
- 2. If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2469 E *lib cmpnt cmpnt id* reported a hardware error.

Explanation: An LSM reported a Hardware Error. This message is from the Event Notification component. Look for a preceding message from ACSLH scsilh that reports the specific hardware error. The library is still operational after a hardware error is reported, but it may be in a degraded mode.

Variable:

• *lib cmpnt* is library component type, e.g., LSM, DRIVE or CAP.

• *cmpnt_id* is the identifier of a library component, e.g., lsm_id, cap_id or drive_id.

Action Required:

1. Review the specific status reported earlier and respond to the problem reported. This may require calling StorageTek Hardware Support.

If this does not fix the problem, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1
 Messages manual). Then contact StorageTek Software Support.

2470 I LSM *lsm id* access door closed.

Explanation: Explanation: The access door of the LSM with value *lsm_id* is closed.

Variable: *lsm id* is the value of LSM identifier.

Action Required: None. This message is informational only.

2471 I LSM lsm id access door opened.

Explanation: The access door of the LSM with value *lsm_id* is open.

Variable: *lsm id* is the value of LSM identifier.

Action Required: None. This message is informational only.

2473 E Failed to add *lib_cmpnt cmpnt_id* into the examine list

Explanation: ACSLS discovered an internal error while examining a library component, e.g., LSM, CAP or drive. To avoid recursive examines, each component being examined is added to a list. This error is reported when a failure in memory allocation prevents the addition of a component to the list.

Variable:

> • *lib cmpnt* is the library component type, e.g., LSM, DRIVE or CAP.

• cmpnt id is the identifier of a library component, e.g., lsm_id, cap_id or drive_id.

Action Required:

- Restart ACSLS.
- If the error continues to be reported, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2474 E Failed to delete lib cmpnt cmpnt id from the examine list

Explanation: ACSLS discovered an internal error while examining library component, e.g., LSM, CAP or drive. The compenent is deleted from the examine list when the examine is completed. This error message indicates that the component has not been deleted from the list.

Variable:

- *lib cmpnt* is the library component type, e.g., LSM, DRIVE or CAP.
- cmpnt id is the identifier of a library component, e.g., lsm_id, cap_id or drive_id.

Action Required:

- Check the component indicated to see if a vary can correct the problem.
- If the error persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

Explanation: The specified volume was marked as absent or ejected in the database, but ACSLS found it in the library. The volume has been reactivated, and its critical information has been preserved.

Variable:

- *vol id* is the absent or ejected volume.
- location_type is the location type (drive or cell) where the cartridge was found.
- *location_id* is the specific drive_id or cell_id where ACSLS found the cartridge.
- vol_type is the volume type (data, scratch, or cleaning).
- access_count is the access count of the volume before it was marked absent.
- pool_id is the pool_id to which the volume belonged before it was marked absent.
- owner_id is the owner of the volume before it was marked absent.

Action Required: None. This message is informational only.

2476 W Volume *vol_id*, not found in *location_type location_id* and was marked absent.

Explanation: Each volume has a home cell and ACSLS can record it as mounted on a drive. ACSLS could not find the specified volume in its recorded location(s), and it has been marked absent in the database to preserve its critical information.

Variable:

- *vol_id* is the absent volume.
- *location type* is the location type (drive or cell) where the volume was recorded and where ACSLS could not find

• location_id is the specific drive_id or cell_id where the volume was recorded but was not found.

Action Required: None. An audit of the ACS or LSM may find the absent volume.

2477 W LSM lsm_id is full; volume vol_id cannot be recovered and is marked absent

> **Explanation:** ACSLS found this volume in the playground/in-transit cell or in a PCP cell while recovering an LSM. It attempted to recover the volume by moving it to a new home cell in this LSM. However, the volume could not be recovered, as the LSM was full, so the volume was marked absent in the database.

Variable:

- *lsm id* identifies the LSM being recovered.
- vol id identifies the absent volume.

Action Required:

- 1. Eject a volume from the LSM.
- 2. Vary the LSM offline and back online to recover the volume.

2478 W LSM Misplaced cartridge detected, volume *vol_id* cannot be recovered and is marked absent

Explanation: ACSLS found this volume in the playground/in–transit cell or in a PCP cell while recovering an LSM. It attempted to recover the volume by moving it to a new home cell in this LSM. However, the move failed because the destination cell contained a cartridge. The volume has not been recovered and is marked absent in the database.

Variable: *vol id* identifies the absent volume.

Action Required:

- Check to make sure that the problem is not a single misplaced cartridge.
- If it is not, audit the LSM to update the ACSLS database to match the actual contents of the library.
- Vary the LSM offline and back offline to recover the volume.

2479 I Volume identifer vol id already found absent

Explanation: The Manual Volume Delete utility (del_vol) was run for a volume that is already marked as absent in the database, but the delete option (-d) was not specified. The volume remains in absent status.

Variable: *vol id* identifies the absent volume.

2480 E EXEC SQL Unable to mark volume *vol_id* as absent because of a database error

Explanation: ACSLS could not find a volume in the library and attempted to mark it absent, but the ACSLS database interface returned an unusual status to the volumetable update. The database update failed.

Variable: *vol id* identifies the absent volume.

Action Required:

- 1. Stop ACSLS (kill.acsss).
- 2. Stop the database (**db_command stop**).
- 3. Kill any hanging ACSLS processes.
- 4. Restart ACSLS (one time).
- 5. If the problem persists, you need the help of ACSLS software support to verify that the table volumetable exists and that the "acsss" user has the proper permissions to update it. Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2481 E EXEC SQL Unable to mark volume vol_id as ejected because of a database error

Explanation: ACSLS ejected a volume and attempted to mark it as ejected. The ACSLS database interface returned an unusual status to a volumetable update. The database update failed.

Variable: vol id identifies the ejected volume.

Action Required:

- 1. Stop ACSLS (kill.acsss).
- 2. Stop the database (**db_command stop**).
- 3. Kill any hanging ACSLS processes.
- 4. Restart ACSLS (one time).

5. If the problem persists, you need the help of ACSLS software support to verify that the table volumetable exists and that the "acsss" user has the proper permissions to update it. Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

2482 E Volume vol id was not found and will be marked absent

Explanation: ACSLS did not find the specified volume in its home cell. If the volume was recorded as mounted on a drive, ACSLS did not find it on the drive. The volume will be marked absent in the database. An audit of the ACS or LSM may find the absent volume.

Variable: *vol_id* identifies the volume that ACSLS did not find.

Action Required: None. This message is informational only.

2483 E License Key expires in nn days: Product product id

Explanation: ACSLS logs this message as the license expiration date approaches, beginning 60 days prior to expiration and specifying the number of days remaining.

Variable:

- nn is the number of days remaining before the license expires.
- product id is the the ACSLS product name and version.

Action Required: Purchase a new license key from StorageTek before the expiration date.

2484 E License Key has expired: Product product id

Explanation: This message warns that your license key has expired. ACSLS will not come up.

Variable: product id is the the ACSLS product name and version.

Action Required: Purchase a new license key from StorageTek.

2485 E License Key information not found: Product product id

Explanation: ACSLS logs this message when license key information is not entered before attempting to bring up the ACSLS server. ACSLS fails to come up.

Variable: product_id is the ACSLS product name and version.

Action Required:

- 1. Run the licensekey.sh script and insert License Key information.
- 2. Run rc.access.

2486 E License Key validation error: Product product id

Explanation: ACSLS logs this message when the licensekey information is entered incorrectly when running the licensekey.sh script or when licensekey information in the database table is tampered with.

Variable: product id is the ACSLS product name and version.

Action Required: Use the licensekey.sh script to re–enter the licensekey information correctly.

2487 E License License library slot capacity exceeded: Product product id, volume count nn, licensed slots ss.

Explanation: ACSLS logs this message when the library volume count exceeds the licensed slot capacity.

Variable:

- product id is the ACSLS product name and version.
- *nn* is the library volume count, excluding Absent/Missing/Ejected cartridges.
- ss is the licensed slot capacity.

Action Required: Either:

- Reduce the number of volumes entered in the library, or
- Purchase a new license that supports more slots from StorageTek.

2488 E EXEC SQL lock timeout on delete from table

Explanation: An attempt to delete a locked record from the database has failed.

Variable: *table* is the name of the locked table

Action Required:

- 1. Restart the application server.
- 2. If the problem persists, restart the database.

2489 E EXEC SQL delete from table failed

Explanation: An attempt to delete records from the table failed.

Variable: *table* is the name of the table.

Action Required:

- 1. Restart the application server.
- 2. If the problem persists, restart the database.

2490 E EXEC SQL select count(col name) from table failed

Explanation: An attempt to count the number of records from the table has failed.

Variable:

- *col_name* is the name of one of the columns in the table.
- *table* is the name of the table.

Action Required:

- 1. Restart the application server.
- 2. If the problem persists, restart the database.

5002 E Received incorrect byte count from input socket: byte_count

Explanation: An internal communication between components has failed.

Variable: byte count is the count of bytes read.

Action Required: Retry the command.

5003 E Received invalid request type: req type

Explanation: An internal communication between components has failed.

Variable: req type is the value of the invalid request.

Action Required: Retry the command.

5004 E Received invalid Sense Code: sense code

Explanation: An internal communication between components has failed.

Variable: *sense code* is the value sent by the hardware.

Action Required: Retry the command.

5005 E Received invalid Status request type: req type

Explanation: An unexpected response was detected from the hardware.

Variable: req type is the value of the invalid status request.

Action Required: Collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

5006 E Unexpected LH failure. Sense code is sense code

Explanation: An unexpected response was detected from the hardware.

Variable: *sense code* is the value sent by the hardware.

Action Required: Verify that the hardware is online. Check the LSM logs for more information.

5007 E Unexpected LSM failure. Sense code is *sense_code*

Explanation: An unexpected response was detected from the hardware.

Variable: *sense code* is the value sent by the hardware.

Action Required: Verify that the hardware is online. Check the LSM logs for more information.

5008 E Received 0 bytes from device: dev name

Explanation: The SCSI device driver may not have been properly installed.

Variable: *dev_name* is the name of the device being opened, i.e., /dev/mchanger4.

Action Required: Verify that the hardware is online. Check the LSM logs for more information.

5009 E No data received after forking process

Explanation: The scsiLh was not able to communicate with the scsiDP. The SCSI device driver may not have been properly installed.

Action Required: Verify that the hardware is online. Check the LSM logs for more information.

5010 E Failed to create UNIX process for device: dev name

Explanation: The scsilh im was not able to communicate with the scsiDP.

Variable: dev name is the name of the device being opened, i.e., /dev/mchanger4.

Action Required: Restart ACSLS and if the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

5011 E Failed to set up read/Wait for process

Explanation: The scsiLh encountered an internal error.

Action Required: Restart ACSLS and if the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

5012 E Starting new UNIX process dev name

Explanation: The scsiDP died and was restarted by the scsilh im.

Variable: *dev_name* is the name of the device being opened, i.e., /dev/mchanger4.

Action Required: Retry the command. and if the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

5013 E Received incorrect byte count from shared memory: $byte_count$

Explanation: An internal communication between components has failed.

Variable: *byte count* is the count of bytes read.

Action Required: Retry the command, and if the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

5014 E Error received from call to smc library: error code

Explanation: An internal communication between components has failed.

Variable: *error_code* is the error code returned by the smc library.

Action Required: Verify that the hardware is online. Check the LSM logs for more information.

5015 E Failed to write to socket: socket name

Explanation: An internal communication between components has failed.

Variable: socket name is the name of the socket.

Action Required: Retry the command, and if the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

5016 E Timed out on request: req name

Explanation: The hardware took longer than expected to respond.

Variable: req name is the name of the request.

Action Required: Verify that the hardware is online. Check the LSM logs for more information. If the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

5017 E Received too many (nnn) bytes in response to internal command: byte count

> **Explanation:** An internal communication between components has failed.

Variable: byte count is the count of bytes read.

Action Required: Retry the command, and if the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

5018 E Unexpected startup data received from process: aString

Explanation: An internal communication between components has failed.

Variable: *aString* is the string that was read from the hardware.

Action Required: Verify that the hardware is online. Check the LSM logs for more information. Retry the command, and if the problem persists, collect relevant ACSLS data (see "Gathering Diagnostic Information for ACSLS Issues" on page four of this ACSLS Version 6.1.1 Messages manual). Then contact StorageTek Software Support.

5019 E Recovering scsiDP: aString

Explanation: A communication error occurred between the library and ACSLS.

Variable: *aString* is the scsiDP process description.

Action Required: None. If you see these messages frequently, you may be experiencing cable problems.

Glossary

absent cartridge—A volume that is in the database, but that couldn't be found when all recorded locations for the volume were catalogued. If a nonzero retention period is set, the volume status is changed to STATUS_VOLUME_ABSENT.

ACS—See Automated Cartridge System.

ACSEL—See ACS Event Logger.

ACS Event Logger (ACSEL)—The software component that receives messages from other ACSLS components and writes them to an Event Log.

ACS ID—A unique identifier for an ACS.

ACSLH—See ACS Library Handler.

ACS library—A library is composed of one or more ACSs, attached tape drives, and cartridges residing in the ACSs.

ACS Library Handler (ACSLH)—The part of the ACSLM that communicates directly with the LMU.

ACSLM—See ACS Library Manager.

ACS Library Manager (ACSLM)—The software component that validates and routes library requests and responses.

ACSLS—See ACS Library Software.

ACSLS database—ACSLS database containing information about the location and status of the tape cartridges. The information includes cell location, scratch status, etc.)

ACSLS platform—The server hardware and software that provide the proper environment for ACSLS.

ACS Library Software (ACSLS)—

Manages ACS library contents and controls ACS library hardware to mount and dismount cartridges on ACS cartridge drives.

ACSLS database—A database used by ACSLS to track the library configuration and the locations and IDs of all tape cartridges in the library.

ACSSA— See ACS System Administrator.

ACS System Administrator

(ACSSA)—The interface between the Command Processor and the rest of the system.

ADI—Application Data Interchange.

audit—A physical inventory of the contents of all or part of a library.

Automated Cartridge System

(ACS)—The library subsystem consisting of a single or dual LMU, and 1 to 24 LSMs connected to that LMU.

automated library—See library.

beginning of tape (BOT)—The location on a tape where written data begins.

BOT— *See* Beginning of Tape.

CAP—See Cartridge Access Port.

CAP ID—A unique identifier for the location of a CAP. A CAP ID consists of the ACS ID, the LSM number, and the CAP number.

cartridge—A plastic housing containing a length of data recording tape. The tape is threaded automatically when loaded in a transport. A plastic leader block is attached to the tape for automatic threading. The spine of the cartridge can contain an OCR/Bar Code label listing the volume ID.

Cartridge Access Port (CAP)—A

bidirectional port built into the door panel of an LSM, which provides for the manual entry or automatic ejection of tape cartridges.

cartridge drive (CD)—A device containing two or four cartridge transports and their associated power and pneumatic supplies.

cartridge tape I/O driver—Operating system software which issues commands (e.g., read, write, and rewind) to cartridge subsystems.

cartridge transport—An

electromechanical device that moves tape from a cartridge over a head that writes and reads data from the tape. A transport is distinct from the power and pneumatic sources that supply the electricity and air it needs to function. *See* cartridge drive.

CCI—See client computing system.

CD—See cartridge drive.

cell—A receptacle in the LSM in which a cartridge is stored.

channel—A device that connects the host and main storage with the input and output control units.

client applications—Software applications that manage tape cartridge contents. They access tape cartridges by interacting with ACSLS. Any number of client applications can be resident on a client system.

client computing system—A computer and an executable image of the operating system.

client software— This software manages tape cartridge contents, generates requests for cartridges, and transfers data to and from cartridges. The client software is *not* part of ACSLS.

Client System Component—Software which provides an interface between the client computing system's operating system and ACSLS.

- Client System Interface (CSI)— The software component that translates and routes messages between the ACS Library Manager and the Client System Component.
- **command access control**—Limits access to commands.
- **command area**—The bottom area of the cmd_proc interface where you enter requests and receive responses.
- **command processor (cmd_proc)** The screen interface of the ACSSA. cmd_proc lets you enter the commands described in Chapter 7.
- **control path adapter**—A hardware device which converts a Client Computing System's control protocol to the control protocol of the StorageTek Library Control System.
- **control unit (CU)**—A microprocessor-based unit logically situated between a channel and up to sixteen cartridge transports. The CU translates channel commands into transport commands and sends transport status to the channel.
- CSE—Customer Services Engineer.
- **CSC**—Client System Component.
- **CSI**—See Client System Interface.
- **CSI variables**—Used to define various options to fine-tune communications between a CSC and the CSI. You change these variables in the acsss_config program.
- CU—See control unit.
- **cycle error messages**—Messages that indicate a library or ACSLS failure.

- **database**—A collection of interrelated data records. *See also* ACSLS Database.
- **data path**—The network path that allows client applications read/write access to tape cartridges.
- data path adapter—A hardware device which translates a Client Computing System's data protocol to the data protocol of the StorageTek Control Unit.
- **display area**—The top area of the cmd_proc interface that collects messages regarding the status of the library.
- **ejected cartridge**—A volume that has been ejected from the library. If a nonzero retention period is set, the volume status is changed to STATUS_VOLUME_EJECTED.
- **end of tape (EOT)** The location on a tape where written data ends.
- **EOT** *See* end of tape.
- **EPO**—Emergency Power Off.
- **EPROM**—*See* erasable programmable read only memory.
- **erasable programmable read-only memory (EPROM)**—A special memory chip that can be erased and reprogrammed.
- **Event Log**—A file, maintained by the ACSEL, that contains messages describing library and ACSLS events.
- **Event Logger**—See ACS Event Logger.

external label identifiers— A

six—character alphanumeric label on the outside edge of a cartridge used to identify a physical tape volume. It may consist of uppercase letters A through Z, numerals 0 through 9, \$, #, and blanks.

full installation—A complete software installation required for new customer sites or for existing sites where a new library has been installed.

home location—The cell associated with a given cartridge.

ID—Identifier or identification.

Informix—The relational database used by ACSLS 6.1.

Informix Storage Manager (ISM)—The Informix database manager, which manages database backups and offloaded transaction logs.

Initial Program Load (IPL)—A process that activates a machine reset, initiates wake up diagnostics (from EPROMs) and loads functional code.

inline diagnostics— Routines that test components of a subsystem while operating on a time-sharing basis with the functional microcode in the subsystem component.

in–transit cartridges—Cartridges between their source and destination locations. Cartridges are considered in–transit if they are in pass–thru ports, robot hands, or playground.

I/O—Input/Output.

IPC—Interprocess Communication.

IPL—See Initial Program Load.

ISM—See Informix Storage Manager.

journal—A sequential log of changes made to the database since the last checkpoint.

LAD— Lock Access Door.

LAN—See local area network.

large CAP (LCAP)—A 40-cartridge CAP with the storage cells arranged in four removable magazines of ten cells each. The magazines appear as a single column of 40 cells to the host software.

LCAP—See large CAP.

LCU—See Library Control Unit.

LED—See Light Emitting Diode.

library—A library is composed of one or more ACSs, attached tape drives, volumes in the ACSs, and the ACSLS software that controls and manages the ACSs.

library configuration options—Allows the customer to specify the number of ACSs in the library and the connections between each ACS and the server system.

library control component—Software which controls the mounting and dismounting of cartridges in the ACS.

library control processor—Properly configured computer hardware that, with the addition of appropriate software, supports the operation of the Library Control Software.

- **library control system**—The library control platform loaded with library control software (ACSLS).
- **library control software**—The software components of ACSLS including the library control component, the Client System Interface and Library Utilities.
- **Library Control Unit**—The portion of the LSM that controls the picking, mounting, dismounting, and replacing of tape cartridges.
- library drive—A cartridge transport attached to an LSM that is connected to, and controlled by, a client system. Library drives interact with the LCU during automated tape cartridge mount and dismount operations. Library drives interact with a client application during tape data transfer operations. Library drives are individually addressable by the ACSLM and are individually accessible by client applications. See Cartridge Transport.
- **library errors**—Errors that occur because the library is offline, has suffered hardware failure, is unavailable, etc.
- **Library Management Unit (LMU)**—The portion of an ACS that manages LSM's, allocates their resources, and communicates with ACSLS.
- **Library Storage Module (LSM)**—An ACS structure that provides the storage area for cartridges, cartridge drives, CAPs, and the robot necessary for moving them.
- **light emitting diode (LED)**—A light emitting device that uses little energy and is used mainly to indicate on/off conditions.
- LMU—See Library Management Unit.

- **local area network** (LAN)—A computer network in which any component in the network can access any other component. This is the type of interface between an LMU and attached LSM's.
- LSM—See Library Storage Module.
- **LSM ID**—A unique identifier for an LSM. The LSM ID consists of the ACS ID and the LSM number.
- missing cartridge—A volume that is in the database, but couldn't be found. If a recorded possible location for the volume could not be examined due to an offline LSM or a drive not communicating, the volume is marked MISSING instead of ABSENT. The volume status is changed to STATUS VOLUME MISSING.
- **network adapter**—Equipment that provides an electrical and logical interface between a network and specific attached equipment.
- **Network Interface (NI)**—An interface between the server system and the client systems that maintains network connections and controls the exchange of messages. The NI is resident on the server system and each client system.
- NI—See Network Interface.
- **OCR**—Optical character recognition.
- **ONC**—Open network computing.

Open Systems Interconnection

(OSI)—A software architecture model of the International Organization for Standardization. The OSI model provides standards for the interconnection of data processing systems.

OSI— See Open Systems Interconnection.

OSLAN—Open Systems Local Area Network.

Pass–Thru Port (PTP)—Mechanism that allows a cartridge to be passed from one LSM to another in a multiple LSM ACS.

PCAP—See priority CAP.

playground—A reserved area of special cells (within an LSM) used for storing diagnostic cartridges and cartridges found in–transit upon power–on and before initialization of the LSM is completed.

pool—A collection of tape cartridges having one or more similar features or attributes, such as a pool of scratch tapes.

POST—Power–on self–test.

priority CAP (PCAP)—A single–cartridge CAP used for priority entry and ejection of cartridges.

processing errors—Errors that result from processing or network communication failures.

PROM—Programmable read-only memory.

PTP—See Pass–Thru Port.

RDBMS—Relational database management system.

redo log files—Backup files used to restore the ACSLS database.

relational database—A database that is organized and accessed according to relationships between the data items; relationships are represented by tables.

ROM—Read—only memory.

RPC—Remote Procedure Call.

SCAP—*See* standard CAP.

scratch—An attribute of a tape cartridge, indicating that it is blank or contains no useful data.

SCSI—Small computer serial interface.

second disk journaling—Allows for the database's journal records to be written to a second disk device, instead of writing records to the primary disk. This improves the chances of recovery from a disk failure.

server system—The part of the library that is the residence for ACSLS, now referred to as the Library Control System. The Library Control System acts as an interface between a library and client systems.

server system user—A person who invokes ACSLS commands, utilities, or procedures on the server system. Server system users are generally site and maintenance personnel (for example, library operators, tape librarians, system administrators, CSEs, and systems personnel).

servo—A system that uses feedback to control a process.

silo—A commonly used term for an LSM. *See* Library Storage Module.

SIMM—Single inline memory module.

SQL—*See* structured query language.

SRN. See service request number.

SSI—See Storage Server Interface.

SSR—Software Support Representative.

Standard CAP (SCAP)—A 21–cartridge CAP with the storage cells arranged in three rows of seven fixed cells.

Storage Server Interface (SSI)—A software component, resident on a client system, that translates and routes messages between client applications and the CSI.

structured query language (**SQL**)—A language used to define, access, and update data in a database.

system resource variable—Used to control the amount of system resources used by ACSLS.

system unit—The Library Control Platform.

tape library management system (TLMS)— A type of client application.

TCP—Transmission Control Protocol.

TLMS—*See* tape library management system.

TOD—Time of day.

UDP—User Datagram Protocol.

UNIX—An operating system originally developed by Bell Laboratories (now UNIX Systems Laboratories, Inc.) and used by a variety of computer systems.

unsolicited messages—Messages that indicate an error or notify you when a particular routine action can be taken.

UOC—Usable on codes.

upgrade installation—Performed when installing a new version of ACSLS at an existing customer site.

user–selectable features and options variables—Used to define various user–selectable features and options.

validation errors—Errors that result from format and syntax validation performed by cmd_proc.

virtual label—A logical label that can be assigned to a cartridge when its physical label is missing or unreadable.

volser—Volume Serial Number.

volume—A tape cartridge.

volume access control—Limits access to volumes, usually by the client.

volume identifier—A six-character string that uniquely identifies a tape cartridge to the database.

volume serial number (volser)—A synonym for external label identifier.

WTM—write tape mark.

XDR— External data representation.

XML—Extensible Markup Language. A universal format for structured documents and/or data on the Web.