

Preparing your Natural/Adabas Environment for Working with Predict

After you have successfully installed Predict, the following parameters must be set before you can start working with Predict.

Natural Parameters

Natural parameters can be changed with the Natural for Windows utility NATPARM. See the **Natural for Windows Operations documentation** for more information.

MADIO	Must be set to 0.
MAXCL	Must be set to 0.
FDIC, FNAT, FUSER	Enter the numbers of the current Predict and Natural system files.
OPRB	OFF.
WORK	Work files 1, 2, 3 and 5 must be specified in DEFAULT format for every Predict user. This can be done by using Windows environment variables as work file names. Set different values for the environment variables for different users.

Adabas Parameters

The following Adabas parameters must be set:

LAB	Must be at least 200,000.
LP	Must be at least 200.
LS	Must be at least 200,000.
LBP	Must be at least 4,000,000.
LWP	Must be at least 1,000,000.
MGC	Must be at least 50.
NC	Must be at least 200.
NH	Must be at least 10,000.
NISNHQ	Must be at least 1,000.
NT	Must be at least 2.
NU	Must be at least 200.
OPTIONS	The option TRUNCATION must be set in the OPTIONS parameter.

Installation Log

If you should encounter any problem during the installation procedure, consult the log files which are written to <Your Path>, where <Your Path> represents the directory you selected as your installation directory.

See Step 6 in the section **Setup and Installation of Predict on Windows** for information on the default installation directory.